

XBinder

XML Schema Compiler
Version 2.0
C XML Runtime
Reference Manual

The software described in this document is furnished under a license agreement and may be used only in accordance with the terms of this agreement.

Copyright Notice

Copyright ©1997-2008 Objective Systems, Inc. All rights reserved.

This document may be distributed in any form, electronic or otherwise, provided that it is distributed in its entirety and that the copyright and this notice are included.

Author's Contact Information

Comments, suggestions, and inquiries regarding XBinder may be submitted via electronic mail to info@obj-sys.com.

Contents

1	Main Page	1
2	C DOM Runtime Library Functions	2
3	Module Index	4
3.1	Modules	4
4	File Index	5
4.1	File List	5
5	Module Documentation	6
5.1	XML decode functions.	6
5.1.1	Function Documentation	8
5.1.1.1	rtXmlDecBase64Binary	8
5.1.1.2	rtXmlDecBase64Str	9
5.1.1.3	rtXmlDecBase64StrValue	9
5.1.1.4	rtXmlDecBigInt	10
5.1.1.5	rtXmlDecBool	10
5.1.1.6	rtXmlDecDate	10
5.1.1.7	rtXmlDecDateTime	11
5.1.1.8	rtXmlDecDecimal	11
5.1.1.9	rtXmlDecDouble	11
5.1.1.10	rtXmlDecDynBase64Str	12
5.1.1.11	rtXmlDecDynHexStr	12
5.1.1.12	rtXmlDecDynUTF8Str	12
5.1.1.13	rtXmlDecGDay	13
5.1.1.14	rtXmlDecGMonth	13
5.1.1.15	rtXmlDecGMonthDay	13
5.1.1.16	rtXmlDecGYear	14
5.1.1.17	rtXmlDecGYearMonth	14

5.1.1.18	rtXmlDecHexBinary	14
5.1.1.19	rtXmlDecHexStr	15
5.1.1.20	rtXmlDecInt	15
5.1.1.21	rtXmlDecInt16	15
5.1.1.22	rtXmlDecInt64	16
5.1.1.23	rtXmlDecInt8	16
5.1.1.24	rtXmlDecNSAttr	17
5.1.1.25	rtXmlDecQName	17
5.1.1.26	rtXmlDecTime	17
5.1.1.27	rtXmlDecUInt	18
5.1.1.28	rtXmlDecUInt16	18
5.1.1.29	rtXmlDecUInt64	19
5.1.1.30	rtXmlDecUInt8	19
5.1.1.31	rtXmlDecUTF8Str	19
5.1.1.32	rtXmlDecXmlStr	20
5.1.1.33	rtXmlDecXSAttr	20
5.1.1.34	rtXmlDecXSAttrs	20
5.1.1.35	rtXmlParseElementName	21
5.1.1.36	rtXmlParseElemQName	21
5.2	XML encode functions	22
5.2.1	Define Documentation	28
5.2.1.1	rtXmlGetEncBufLen	28
5.2.1.2	rtXmlGetEncBufPtr	28
5.2.2	Function Documentation	28
5.2.2.1	rtXmlEncAny	28
5.2.2.2	rtXmlEncAnyAttr	29
5.2.2.3	rtXmlEncAnyTypeValue	29
5.2.2.4	rtXmlEncBase64Binary	29
5.2.2.5	rtXmlEncBase64BinaryAttr	30
5.2.2.6	rtXmlEncBase64StrValue	30
5.2.2.7	rtXmlEncBigInt	31
5.2.2.8	rtXmlEncBigIntAttr	31
5.2.2.9	rtXmlEncBigIntValue	31
5.2.2.10	rtXmlEncBinStrValue	32
5.2.2.11	rtXmlEncBitString	32
5.2.2.12	rtXmlEncBOM	33
5.2.2.13	rtXmlEncBool	33

5.2.2.14	rtXmlEncBoolAttr	33
5.2.2.15	rtXmlEncBoolValue	34
5.2.2.16	rtXmlEncDate	34
5.2.2.17	rtXmlEncDateTime	34
5.2.2.18	rtXmlEncDateTimeValue	35
5.2.2.19	rtXmlEncDateValue	35
5.2.2.20	rtXmlEncDecimal	35
5.2.2.21	rtXmlEncDecimalAttr	36
5.2.2.22	rtXmlEncDecimalValue	36
5.2.2.23	rtXmlEncDouble	37
5.2.2.24	rtXmlEncDoubleAttr	37
5.2.2.25	rtXmlEncDoubleValue	37
5.2.2.26	rtXmlEncEmptyElement	38
5.2.2.27	rtXmlEncEndDocument	38
5.2.2.28	rtXmlEncEndElement	39
5.2.2.29	rtXmlEncEndSoapElems	39
5.2.2.30	rtXmlEncEndSoapEnv	39
5.2.2.31	rtXmlEncFloat	40
5.2.2.32	rtXmlEncFloatAttr	40
5.2.2.33	rtXmlEncGDay	40
5.2.2.34	rtXmlEncGDayValue	41
5.2.2.35	rtXmlEncGMonth	41
5.2.2.36	rtXmlEncGMonthDay	42
5.2.2.37	rtXmlEncGMonthDayValue	42
5.2.2.38	rtXmlEncGMonthValue	42
5.2.2.39	rtXmlEncGYear	43
5.2.2.40	rtXmlEncGYearMonth	43
5.2.2.41	rtXmlEncGYearMonthValue	43
5.2.2.42	rtXmlEncGYearValue	44
5.2.2.43	rtXmlEncHexBinary	44
5.2.2.44	rtXmlEncHexBinaryAttr	44
5.2.2.45	rtXmlEncHexStrValue	45
5.2.2.46	rtXmlEncIndent	45
5.2.2.47	rtXmlEncInt	45
5.2.2.48	rtXmlEncInt64	46
5.2.2.49	rtXmlEncInt64Attr	46
5.2.2.50	rtXmlEncInt64Value	47

5.2.2.51	rtXmlEncIntAttr	47
5.2.2.52	rtXmlEncIntPattern	47
5.2.2.53	rtXmlEncIntValue	48
5.2.2.54	rtXmlEncNamedBits	48
5.2.2.55	rtXmlEncNSAttrs	49
5.2.2.56	rtXmlEncReal10	49
5.2.2.57	rtXmlEncSoapArrayTypeAttr	49
5.2.2.58	rtXmlEncStartDocument	50
5.2.2.59	rtXmlEncStartElement	50
5.2.2.60	rtXmlEncStartSoapElems	51
5.2.2.61	rtXmlEncStartSoapEnv	51
5.2.2.62	rtXmlEncString	51
5.2.2.63	rtXmlEncStringValue	52
5.2.2.64	rtXmlEncStringValue2	52
5.2.2.65	rtXmlEncTermStartElement	52
5.2.2.66	rtXmlEncTime	53
5.2.2.67	rtXmlEncTimeValue	53
5.2.2.68	rtXmlEncUInt	53
5.2.2.69	rtXmlEncUInt64	54
5.2.2.70	rtXmlEncUInt64Attr	54
5.2.2.71	rtXmlEncUInt64Value	55
5.2.2.72	rtXmlEncUIntAttr	55
5.2.2.73	rtXmlEncUIntValue	55
5.2.2.74	rtXmlEncUnicodeStr	56
5.2.2.75	rtXmlEncUTF8Attr	56
5.2.2.76	rtXmlEncUTF8Attr2	56
5.2.2.77	rtXmlEncUTF8Str	57
5.2.2.78	rtXmlEncXSAttrs	57
5.2.2.79	rtXmlEncXSTypeAttr	58
5.2.2.80	rtXmlFreeInputSource	58
5.2.2.81	rtXmlGetIndent	58
5.2.2.82	rtXmlGetIndentChar	58
5.2.2.83	rtXmlGetWriteBOM	59
5.2.2.84	rtXmlPrintNSAttrs	59
5.2.2.85	rtXmlSetEncBufPtr	59
5.3	XML utility functions.	60
5.3.1	Function Documentation	60

5.3.1.1	rtXmlWriteToFile	60
5.4	XML pull-parser decode functions.	61
5.4.1	Function Documentation	65
5.4.1.1	rtXmlEncAttrC14N	65
5.4.1.2	rtXmlpCountListItems	66
5.4.1.3	rtXmlpCreateReader	66
5.4.1.4	rtXmlpDecAny	66
5.4.1.5	rtXmlpDecAnyAttrStr	67
5.4.1.6	rtXmlpDecAnyElem	67
5.4.1.7	rtXmlpDecBase64Str	67
5.4.1.8	rtXmlpDecBigInt	68
5.4.1.9	rtXmlpDecBitString	68
5.4.1.10	rtXmlpDecBool	69
5.4.1.11	rtXmlpDecDate	69
5.4.1.12	rtXmlpDecDateTime	69
5.4.1.13	rtXmlpDecDecimal	70
5.4.1.14	rtXmlpDecDouble	70
5.4.1.15	rtXmlpDecDynBase64Str	70
5.4.1.16	rtXmlpDecDynBitString	71
5.4.1.17	rtXmlpDecDynHexStr	71
5.4.1.18	rtXmlpDecDynUnicodeStr	72
5.4.1.19	rtXmlpDecDynUTF8Str	72
5.4.1.20	rtXmlpDecGDay	72
5.4.1.21	rtXmlpDecGMonth	73
5.4.1.22	rtXmlpDecGMonthDay	73
5.4.1.23	rtXmlpDecGYear	73
5.4.1.24	rtXmlpDecGYearMonth	74
5.4.1.25	rtXmlpDecHexStr	74
5.4.1.26	rtXmlpDecInt	75
5.4.1.27	rtXmlpDecInt16	75
5.4.1.28	rtXmlpDecInt64	75
5.4.1.29	rtXmlpDecInt8	76
5.4.1.30	rtXmlpDecNamedBits	76
5.4.1.31	rtXmlpDecStrList	76
5.4.1.32	rtXmlpDecTime	77
5.4.1.33	rtXmlpDecUInt	77
5.4.1.34	rtXmlpDecUInt16	77

5.4.1.35	rtXmlpDecUInt64	78
5.4.1.36	rtXmlpDecUInt8	78
5.4.1.37	rtXmlpDecUTF8Str	78
5.4.1.38	rtXmlpDecXmlStr	79
5.4.1.39	rtXmlpDecXmlStrList	79
5.4.1.40	rtXmlpDecXSIAAttr	80
5.4.1.41	rtXmlpDecXSIAAttrs	80
5.4.1.42	rtXmlpDecXSITypeAttr	80
5.4.1.43	rtXmlpForceDecodeAsGroup	81
5.4.1.44	rtXmlpGetAttributeCount	81
5.4.1.45	rtXmlpGetAttributeID	81
5.4.1.46	rtXmlpGetCurrentLevel	82
5.4.1.47	rtXmlpGetNextAllElemID	82
5.4.1.48	rtXmlpGetNextAllElemID16	82
5.4.1.49	rtXmlpGetNextElem	83
5.4.1.50	rtXmlpGetNextElemID	83
5.4.1.51	rtXmlpGetNextSeqElemID	84
5.4.1.52	rtXmlpGetXmInsAttrs	84
5.4.1.53	rtXmlpGetXSITypeAttr	84
5.4.1.54	rtXmlpGetXSITypeIndex	85
5.4.1.55	rtXmlpHasAttributes	85
5.4.1.56	rtXmlpHideAttributes	85
5.4.1.57	rtXmlpIsDecodeAsGroup	86
5.4.1.58	rtXmlpIsEmptyElement	86
5.4.1.59	rtXmlpIsLastEventDone	86
5.4.1.60	rtXmlpIsUTF8Encoding	86
5.4.1.61	rtXmlpListHasItem	87
5.4.1.62	rtXmlpLookupXSITypeIndex	87
5.4.1.63	rtXmlpMarkLastEventActive	87
5.4.1.64	rtXmlpMarkPos	88
5.4.1.65	rtXmlpMatchEndTag	88
5.4.1.66	rtXmlpMatchStartTag	88
5.4.1.67	rtXmlpNeedDecodeAttributes	88
5.4.1.68	rtXmlpResetMarkedPos	89
5.4.1.69	rtXmlpRewindToMarkedPos	89
5.4.1.70	rtXmlpSelectAttribute	89
5.4.1.71	rtXmlpSetListMode	89

5.4.1.72	rtXmlpSetMixedContentMode	90
5.4.1.73	rtXmlpSetNamespaceTable	90
5.4.1.74	rtXmlpSetWhiteSpaceMode	90
5.5	XML run-time error status codes.	91
5.5.1	Detailed Description	92
5.5.2	Define Documentation	92
5.5.2.1	XML_E_BASE	92
5.5.2.2	XML_E_ELEMMISRQ	92
5.5.2.3	XML_E_ELEMSISRQ	93
5.5.2.4	XML_E_FLDABSENT	93
5.5.2.5	XML_E_NOMATCH	93
5.5.2.6	XML_E_NSURINOTFOU	93
5.5.2.7	XML_E_TAGMISMATCH	93
5.5.2.8	XML_OK_EOB	93
5.5.2.9	XML_OK_FRAG	93
5.6	DOM API functions.	94
5.6.1	Function Documentation	95
5.6.1.1	domAddAttribute	95
5.6.1.2	domAddCdata	96
5.6.1.3	domAddContent	96
5.6.1.4	domCreateChild	96
5.6.1.5	domCreateDocument	97
5.6.1.6	domFreeDoc	97
5.6.1.7	domGetAttrData	97
5.6.1.8	domGetChild	98
5.6.1.9	domGetDoc	98
5.6.1.10	domGetElementName	98
5.6.1.11	domGetNext	98
5.6.1.12	domGetNextAttr	99
5.6.1.13	domGetNodeAttributesNum	99
5.6.1.14	domGetNodeContent	99
5.6.1.15	domGetNodeFirstAttribute	100
5.6.1.16	domGetRootElement	100
5.6.1.17	domParseFile	100
5.6.1.18	domSaveDoc	100
5.7	DOM runtime encode/decode functions.	102
5.7.1	Function Documentation	103

5.7.1.1	rtDomAddAttr	103
5.7.1.2	rtDomAddNode	103
5.7.1.3	rtDomAddNSAttrs	104
5.7.1.4	rtDomAddSubTree	104
5.7.1.5	rtDomDecodeDoc	104
5.7.1.6	rtDomEncAny	105
5.7.1.7	rtDomEncAnyAttr	105
5.7.1.8	rtDomEncString	106
5.7.1.9	rtDomEncStringValue	106
5.7.1.10	rtDomEncXSIAttrs	106
5.7.1.11	rtDomSetNode	107
6	File Documentation	108
6.1	osrtdom.h File Reference	108
6.1.1	Detailed Description	109
6.2	osrxml.h File Reference	110
6.2.1	Detailed Description	126
6.2.2	Function Documentation	126
6.2.2.1	rtSaxGetAttrValue	126
6.2.2.2	rtSaxGetElemID	126
6.2.2.3	rtSaxGetElemID8	126
6.2.2.4	rtSaxHasXMLNSAttrs	127
6.2.2.5	rtSaxIsEmptyBuffer	127
6.2.2.6	rtSaxSortAttrs	127
6.2.2.7	rtSaxStrListMatch	128
6.2.2.8	rtSaxStrListParse	128
6.2.2.9	rtXmlCmpBase64Str	128
6.2.2.10	rtXmlCmpHexStr	128
6.2.2.11	rtXmlCreateFileInputSource	129
6.2.2.12	rtXmlInitContext	129
6.2.2.13	rtXmlInitCtxtAppInfo	129
6.2.2.14	rtXmlMatchBase64Str	129
6.2.2.15	rtXmlMatchDate	130
6.2.2.16	rtXmlMatchDateTime	130
6.2.2.17	rtXmlMatchGDay	130
6.2.2.18	rtXmlMatchGMonth	131
6.2.2.19	rtXmlMatchGMonthDay	131

6.2.2.20	rtXmlMatchGYear	131
6.2.2.21	rtXmlMatchGYearMonth	131
6.2.2.22	rtXmlMatchHexStr	132
6.2.2.23	rtXmlMatchTime	132
6.2.2.24	rtXmlMemFreeAnyAttrs	132
6.2.2.25	rtXmlNewQName	132
6.2.2.26	rtXmlPrepareContext	133
6.2.2.27	rtXmlSetEncC14N	133
6.2.2.28	rtXmlSetEncDocHdr	133
6.2.2.29	rtXmlSetEncodingStr	133
6.2.2.30	rtXmlSetEncXSINamespace	134
6.2.2.31	rtXmlSetFormatting	134
6.2.2.32	rtXmlSetIndent	134
6.2.2.33	rtXmlSetIndentChar	134
6.2.2.34	rtXmlSetNamespacesSet	135
6.2.2.35	rtXmlSetNoNSSchemaLocation	135
6.2.2.36	rtXmlSetNSPrefixLinks	135
6.2.2.37	rtXmlSetSchemaLocation	136
6.2.2.38	rtXmlSetSoapVersion	136
6.2.2.39	rtXmlSetWriteBOM	136
6.2.2.40	rtXmlSetXSITypeAttr	136
6.3	rtXmlErrCodes.h File Reference	137
6.3.1	Detailed Description	138
6.4	rtXmlExternDefs.h File Reference	139
6.4.1	Detailed Description	139
6.5	rtXmlKeyArray.h File Reference	140
6.5.1	Detailed Description	140
6.6	rtXmlNamespace.h File Reference	141
6.6.1	Detailed Description	143
6.6.2	Define Documentation	143
6.6.2.1	RTXMLNSSETQNAME	143
6.6.3	Function Documentation	143
6.6.3.1	rtXmlNSAddNamespace	143
6.6.3.2	rtXmlNSEqual	143
6.6.3.3	rtXmlNSFreeAttrList	144
6.6.3.4	rtXmlNSGetAttrQName	144
6.6.3.5	rtXmlNSGetPrefix	144

6.6.3.6	<code>rtXmlNSGetPrefixCount</code>	145
6.6.3.7	<code>rtXmlNSGetPrefixIndex</code>	145
6.6.3.8	<code>rtXmlNSGetPrefixUsingIndex</code>	145
6.6.3.9	<code>rtXmlNSGetQName</code>	146
6.6.3.10	<code>rtXmlNSLookupPrefix</code>	146
6.6.3.11	<code>rtXmlNSLookupPrefixFrag</code>	146
6.6.3.12	<code>rtXmlNSLookupURI</code>	147
6.6.3.13	<code>rtXmlNSLookupURIInList</code>	147
6.6.3.14	<code>rtXmlNSNewPrefix</code>	147
6.6.3.15	<code>rtXmlNSRemoveAll</code>	147
6.6.3.16	<code>rtXmlNSSetNamespace</code>	148
6.7	<code>rtXmlpCppDecFuncs.h</code> File Reference	149
6.7.1	Detailed Description	149

Chapter 1

Main Page

C XML Runtime Library Functions

The **C run-time XML library** contains functions used to encode/decode XML data. These functions are identified by their *rtXml* prefixes.

The categories of functions provided are as follows:

- XML pull-parser code.
- Functions functions to encode C types to XML.
- Functions to decode XML to C data types.
- Functions to encode XML element tags.
- Functions to encode XML attributes in sorted order for C14N.
- SAX parser interfaces.
- Context management functions.

Chapter 2

C DOM Runtime Library Functions

The **C run-time DOM library** contains functions used to encode/decode XML data in a DOM tree. These functions are identified by their *rtDom* prefixes.

The categories of functions provided are as follows:

- Functions to add nodes.
- Functions to add attributes to a node.
- Functions to add namespace and xsi:type information.
- Functions to encode data types to DOM.

Chapter 3

Module Index

3.1 Modules

Here is a list of all modules:

XML decode functions.	6
XML encode functions.	22
XML utility functions.	60
XML pull-parser decode functions.	61
XML run-time error status codes.	91
DOM API functions.	94
DOM runtime encode/decode functions.	102

Chapter 4

File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

domAPI.h	??
osrtdom.h (DOM low-level C encode/decode functions)	108
osrtxml.h (XML low-level C encode/decode functions)	110
rtLx2Dom.h	??
rtxDomDefs.h	??
rtXmlErrCodes.h (List of numeric status codes that can be returned by ASN1C run-time functions and generated code)	137
rtXmlExternDefs.h (XML external definitions macro)	139
rtXmlKeyArray.h	(
• Implementation of a dynamic pointer sorted array	
)	140
rtXmlNamespace.h (XML namespace handling structures and function definitions)	141
rtXmlpCppDecFuncs.h (XML low-level C++ decode functions)	149
rtXmlPull.h	??

Chapter 5

Module Documentation

5.1 XML decode functions.

Functions

- int [rtXmlDecBase64Binary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, int length)
This function decodes the contents of a Base64-encoded binary data type into a memory buffer.
- int [rtXmlDecBase64Str](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int [rtXmlDecBase64StrValue](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, size_t bufSize, size_t srcDataLen)
This function decodes a contents of a Base64-encode binary string into the specified octet array.
- int [rtXmlDecBigInt](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppvalue)
This function will decode a variable of the XSD integer type.
- int [rtXmlDecBool](#) (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int [rtXmlDecDate](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int [rtXmlDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.
- int [rtXmlDecDateTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int [rtXmlDecDecimal](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a decimal data type.
- int [rtXmlDecDouble](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.

- int [rtXmlDecDynBase64Str](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int [rtXmlDecDynHexStr](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int [rtXmlDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *outdata, size_t max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecHexBinary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, int length)
This function decodes the contents of a hex-encoded binary data type into a memory buffer.
- int [rtXmlDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int [rtXmlDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.
- int [rtXmlDecUInt8](#) (OSCTXT *pctxt, OSUINT8 *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.

- int [rtXmlDecUInt16](#) (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int [rtXmlDecUInt64](#) (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.
- int [rtXmlDecNSAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue, OSRTDList *pNSAttrs, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)
This function decodes an XML namespace attribute (xmlns).
- const OSUTF8CHAR * [rtXmlDecQName](#) (OSCTXT *pctxt, const OSUTF8CHAR *qname, const OSUTF8CHAR **prefix)
This function decodes an XML qualified name string (QName) type.
- int [rtXmlDecXSIAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue)
This function decodes XML schema instance (XSI) attribute.
- int [rtXmlDecXSIAttrs](#) (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, const char *typeName)
This function decodes XML schema instance (XSI) attributes.
- int [rtXmlDecXmlStr](#) (OSCTXT *pctxt, OSXMLSTRING *outdata)
This function decodes the contents of an XML string data type.
- int [rtXmlParseElementName](#) (OSCTXT *pctxt, OSUTF8CHAR **ppName)
This function parses the initial tag from an XML message.
- int [rtXmlParseElemQName](#) (OSCTXT *pctxt, OSXMLQName *pQName)
This function parses the initial tag from an XML message.

5.1.1 Function Documentation

5.1.1.1 int [rtXmlDecBase64Binary](#) (OSRTMEMBUF * *pMemBuf*, const OSUTF8CHAR * *inpdata*, int *length*)

This function decodes the contents of a Base64-encoded binary data type into a memory buffer.

Input is expected to be a string of UTF-8 characters returned by an XML parser. The decoded data will be put into the memory buffer starting from the current position and bit offset. After all data is decoded the octet string may be fetched out.

This function is normally used in the 'characters' SAX handler.

Parameters:

- pMemBuf* Memory buffer to which decoded binary data is to be appended.
- inpdata* Pointer to a source string to be decoded.
- length* Length of the source string (in characters).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.2 **int rtXmlDecBase64Str (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)**

This function decodes a contents of a Base64-encode binary string into a static memory structure.

The octet string must be Base64 encoded. This function call is used to decode a sized base64Binary string production.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the *bufsize* input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.3 **int rtXmlDecBase64StrValue (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, size_t *bufSize*, size_t *srcDataLen*)**

This function decodes a contents of a Base64-encode binary string into the specified octet array.

The octet string must be Base64 encoded. This function call is used internally to decode both sized and non-sized base64binary string production.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the *bufsize* input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufSize A maximum size (in octets) of *pvalue* buffer. An error will occur if the number of octets in the decoded string is larger than this value.

srcDataLen An actual source data length (in octets) without whitespaces.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.4 **int rtXmlDecBigInt (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppvalue*)**

This function will decode a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

These variables are stored in character string constant variables. The radix should be 10. If it is necessary to convert to another radix, then use `rtxBigIntSetStr` or `rtxBigIntToString` functions.

Parameters:

pctxt Pointer to context block structure.

ppvalue Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the `rtMemAlloc` function. The decoded variable is represented as a string starting with appropriate prefix.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.5 **int rtXmlDecBool (OSCTXT * *pctxt*, OSBOOL * *pvalue*)**

This function decodes a variable of the boolean type.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.6 **int rtXmlDecDate (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'date' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY-MM-DD format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.7 **int rtXmlDecDateTime (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'dateTime' type.

Input is expected to be a string of characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.8 **int rtXmlDecDecimal (OSCTXT * *pctxt*, OSREAL * *pvalue*)**

This function decodes the contents of a decimal data type.

Input is expected to be a string of characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.9 **int rtXmlDecDouble (OSCTXT * *pctxt*, OSREAL * *pvalue*)**

This function decodes the contents of a float or double data type.

Input is expected to be a string of characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.10 `int rtXmlDecDynBase64Str (OSCTXT * pctxt, OSDynOctStr * pvalue)`

This function decodes a contents of a Base64-encode binary string.

The octet string must be Base64 encoded. This function will allocate dynamic memory to store the decoded result.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the `rtxMemAlloc` function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.11 `int rtXmlDecDynHexStr (OSCTXT * pctxt, OSDynOctStr * pvalue)`

This function decodes a contents of a hexBinary string.

This function will allocate dynamic memory to store the decoded result.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the `rtxMemAlloc` function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.12 `int rtXmlDecDynUTF8Str (OSCTXT * pctxt, const OSUTF8CHAR ** outdata)`

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of UTF-8 or Unicode characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

outdata Pointer to a pointer to receive decoded UTF-8 string. Memory is allocated for this string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.13 `int rtXmlDecGDay (OSCTXT * pctxt, OSXSDDateTime * pvalue)`

This function decodes a variable of the XSD 'gDay' type.

Input is expected to be a string of characters returned by an XML parser. The string should have —DD[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.14 `int rtXmlDecGMonth (OSCTXT * pctxt, OSXSDDateTime * pvalue)`

This function decodes a variable of the XSD 'gMonth' type.

Input is expected to be a string of characters returned by an XML parser. The string should have –MM[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.15 `int rtXmlDecGMonthDay (OSCTXT * pctxt, OSXSDDateTime * pvalue)`

This function decodes a variable of the XSD 'gMonthDay' type.

Input is expected to be a string of characters returned by an XML parser. The string should have –MM-DD[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.16 **int rtXmlDecGYear (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gYear' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY[-+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.17 **int rtXmlDecGYearMonth (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gYearMonth' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY-MM[-+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.18 **int rtXmlDecHexBinary (OSRTMEMBUF * *pMemBuf*, const OSUTF8CHAR * *inpdata*, int *length*)**

This function decodes the contents of a hex-encoded binary data type into a memory buffer.

Input is expected to be a string of UTF-8 characters returned by an XML parser. The decoded data will be put into the given memory buffer starting from the current position and bit offset. After all data is decoded the octet string may be fetched out.

This function is normally used in the 'characters' SAX handler.

Parameters:

pMemBuf Pointer to memory buffer onto which the decoded binary data will be appended.

inpdata Pointer to a source string to be decoded.

length Length of the source string (in characters).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.19 int rtXmlDecHexStr (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)

This function decodes the contents of a hexBinary string into a static memory structure.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the *bufsize* input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.20 int rtXmlDecInt (OSCTXT * *pctxt*, OSINT32 * *pvalue*)

This function decodes the contents of a 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 32-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.21 int rtXmlDecInt16 (OSCTXT * *pctxt*, OSINT16 * *pvalue*)

This function decodes the contents of a 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 16-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.22 int rtXmlDecInt64 (OSCTXT * *pctxt*, OSINT64 * *pvalue*)

This function decodes the contents of a 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.23 int rtXmlDecInt8 (OSCTXT * *pctxt*, OSINT8 * *pvalue*)

This function decodes the contents of an 8-bit integer data type (i.e.

a signed byte type in the range of -128 to 127). Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 8-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.24 `int rtXmlDecNSAttr (OSCTXT * pctxt, const OSUTF8CHAR * attrName, const OSUTF8CHAR * attrValue, OSRTDList * pNSAttrs, const OSUTF8CHAR * nsTable[], OSUINT32 nsTableRowCount)`

This function decodes an XML namespace attribute (xmlns).

It is assumed that the given attribute name is either 'xmlns' or 'xmlns:prefix'. The XML namespace prefix and URI are added to the given attribute list structure. The parsed namespace is also added to the namespace stack in the given context.

Parameters:

pctxt Pointer to context structure.

attrName Name of the XML namespace attribute. This is assumed to contain either 'xmlns' (a default namespace declaration) or 'xmlns:prefix' where prefix is a namespace prefix.

attrValue XML namespace attribute value (a URI).

pNSAttrs List to receive parsed namespace values.

nsTable Namespace URI's parsed from schema.

nsTableRowCount Number of rows (URI's) in namespace table.

Returns:

Zero if success or negative error code.

5.1.1.25 `const OSUTF8CHAR* rtXmlDecQName (OSCTXT * pctxt, const OSUTF8CHAR * qname, const OSUTF8CHAR ** prefix)`

This function decodes an XML qualified name string (QName) type.

This is a type that contains an optional namespace prefix followed by a colon and the local part of the name:

[NS 5] QName ::= (Prefix ':')? LocalPart

[NS 6] Prefix ::= NCName

[NS 7] LocalPart ::= NCName

Parameters:

pctxt Pointer to context block structure.

qname String containing XML QName to be decoded.

prefix Pointer to string pointer to receive decoded prefix. This is optional. If NULL, the prefix will not be returned. If not-NULL, the prefix will be returned in memory allocated using `rtxMemAlloc` which must be freed using one of the `rtxMemFree` functions.

Returns:

Pointer to local part of string. This is pointer to a location within the given string (i.e. a pointer to the character after the ':' or to the beginning of the string if it contains no colon). This pointer does not need to be freed.

5.1.1.26 `int rtXmlDecTime (OSCTXT * pctxt, OSXSDDateTime * pvalue)`

This function decodes a variable of the XSD 'time' type.

Input is expected to be a string of characters returned by an XML parser. The string should have one of following formats:

(1) hh-mm-ss.ss used if tz_flag = false (2) hh-mm-ss.ssZ used if tz_flag = false and tzo = 0 (3) hh-mm-ss.ss+HH:MM if tz_flag = false and tzo > 0 (4) hh-mm-ss.ss-HH:MM-HH:MM if tz_flag = false and tzo < 0

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.27 int rtXmlDecUInt (OSCTXT * *pctxt*, OSUINT32 * *pvalue*)

This function decodes the contents of an unsigned 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 32-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.28 int rtXmlDecUInt16 (OSCTXT * *pctxt*, OSUINT16 * *pvalue*)

This function decodes the contents of an unsigned 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 16-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.29 `int rtXmlDecUInt64 (OSCTXT * pctxt, OSUINT64 * pvalue)`

This function decodes the contents of an unsigned 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 64-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.30 `int rtXmlDecUInt8 (OSCTXT * pctxt, OSUINT8 * pvalue)`

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

a signed byte type in the range of 0 to 255). Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 8-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.31 `int rtXmlDecUTF8Str (OSCTXT * pctxt, OSUTF8CHAR * outdata, size_t max_len)`

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of UTF-8 or Unicode characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

outdata Pointer to a block of memory to receive decoded UTF8 string.

max_len Size of memory block.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.32 `int rtXmlDecXmlStr (OSCTXT * pctxt, OSXMLSTRING * outdata)`

This function decodes the contents of an XML string data type.

This type contains a pointer to a UTF-8 character string plus flags that can be set to alter the encoding of the string (for example, the `cdata` flag allows the string to be encoded in a CDATA section). Input is expected to be a string of UTF-8 characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

outdata Pointer to an XML string structure to receive the decoded string. Memory is allocated for the string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.33 `int rtXmlDecXSIAttr (OSCTXT * pctxt, const OSUTF8CHAR * attrName, const OSUTF8CHAR * attrValue)`

This function decodes XML schema instance (XSI) attribute.

These attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

Parameters:

pctxt Pointer to context block structure.

attrName Attribute's name to be decoded

attrValue Attribute's value to be decoded

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.34 `int rtXmlDecXSIAttrs (OSCTXT * pctxt, const OSUTF8CHAR *const * attrs, const char * typeName)`

This function decodes XML schema instance (XSI) attributes.

These attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

Parameters:

pctxt Pointer to context block structure.

attrs Attributes-values array [attr, value]. Should be null-terminated.

typeName Name of parent type to add in error log, if would be necessary.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.35 int rtXmlParseElementName (OSCTXT * *pctxt*, OSUTF8CHAR ** *ppName*)

This function parses the initial tag from an XML message.

If the tag is a QName, only the local part of the name is returned.

Parameters:

pctxt Pointer to OSCTXT structure

ppName Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the rtxMemAlloc function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.1.1.36 int rtXmlParseElemQName (OSCTXT * *pctxt*, OSXMLQName * *pQName*)

This function parses the initial tag from an XML message.

Parameters:

pctxt Pointer to OSCTXT structure

pQName Pointer to a QName structure to receive parsed name prefix and local name. Dynamic memory is allocated for both name parts using the rtxMemAlloc function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2 XML encode functions.

Defines

- #define `rtXmlGetEncBufPtr`(pctx) (pctx) → buffer.data
This macro returns the start address of the encoded XML message.
- #define `rtXmlGetEncBufLen`(pctx) (pctx) → buffer.byteIndex
This macro returns the length of the encoded XML message.

Functions

- int `rtXmlEncAny` (OSCTXT *pctx, OSXMLSTRING *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD any type.
- int `rtXmlEncAnyTypeValue` (OSCTXT *pctx, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD anyType type.
- int `rtXmlEncAnyAttr` (OSCTXT *pctx, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- int `rtXmlEncBase64Binary` (OSCTXT *pctx, OSUINT32 noctx, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD base64Binary type.
- int `rtXmlEncBase64BinaryAttr` (OSCTXT *pctx, OSUINT32 noctx, const OSOCTET *value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD base64Binary type as an attribute.
- int `rtXmlEncBase64StrValue` (OSCTXT *pctx, OSUINT32 noctx, const OSOCTET *value)
This function encodes a variable of the XSD base64Binary type.
- int `rtXmlEncBigInt` (OSCTXT *pctx, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncBigIntAttr` (OSCTXT *pctx, const OSUTF8CHAR *value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes an XSD integer attribute value.
- int `rtXmlEncBigIntValue` (OSCTXT *pctx, const OSUTF8CHAR *value)
This function encodes an XSD integer attribute value.
- int `rtXmlEncBitString` (OSCTXT *pctx, OSUINT32 nbits, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 BIT STRING type.
- int `rtXmlEncBinStrValue` (OSCTXT *pctx, OSUINT32 nbits, const OSOCTET *data)

This function encodes a binary string value as a sequence of '1's and '0's.

- int [rtXmlEncBool](#) (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD boolean type.
- int [rtXmlEncBoolValue](#) (OSCTXT *pctxt, OSBOOL value)
This function encodes a variable of the XSD boolean type.
- int [rtXmlEncBoolAttr](#) (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes an XSD boolean attribute value.
- int [rtXmlEncDate](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'date' type as a string.
- int [rtXmlEncDateValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a variable of the XSD 'date' type as a string.
- int [rtXmlEncTime](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'time' type as a string.
- int [rtXmlEncTimeValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a variable of the XSD 'time' type as a string.
- int [rtXmlEncDateTime](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric date/time value into an XML string representation.
- int [rtXmlEncDateTimeValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric date/time value into an XML string representation.
- int [rtXmlEncDecimal](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDecimalFmt *pFmtSpec)
This function encodes a variable of the XSD decimal type.
- int [rtXmlEncDecimalAttr](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDecimalFmt *pFmtSpec)
This function encodes a variable of the XSD decimal type as an attribute.
- int [rtXmlEncDecimalValue](#) (OSCTXT *pctxt, OSREAL value, const OSDecimalFmt *pFmtSpec, char *pDestBuf, size_t destBufSize)
This function encodes a value of the XSD decimal type.
- int [rtXmlEncDouble](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD double type.

- int [rtXmlEncDoubleAttr](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD double type as an attribute.
- int [rtXmlEncDoubleValue](#) (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)
This function encodes a value of the XSD double or float type.
- int [rtXmlEncEmptyElement](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)
This function encodes an empty element tag value (<elemName/>).
- int [rtXmlEncEndDocument](#) (OSCTXT *pctxt)
This function adds trailer information and a null terminator at the end of the XML document being encoded.
- int [rtXmlEncEndElement](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes an end element tag value (</elemName>).
- int [rtXmlEncEndSoapEnv](#) (OSCTXT *pctxt)
This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).
- int [rtXmlEncEndSoapElems](#) (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)
This function encodes SOAP end element tags.
- int [rtXmlEncFloat](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD float type.
- int [rtXmlEncFloatAttr](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD float type as an attribute.
- int [rtXmlEncGYear](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gYear element into an XML string representation.
- int [rtXmlEncGYearMonth](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gYearMonth element into an XML string representation.
- int [rtXmlEncGMonth](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gMonth element into an XML string representation.
- int [rtXmlEncGMonthDay](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gMonthDay element into an XML string representation.
- int [rtXmlEncGDay](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gDay element into an XML string representation.

- int [rtXmlEncGYearValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gYear value into an XML string representation.
- int [rtXmlEncGYearMonthValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gYearMonth value into an XML string representation.
- int [rtXmlEncGMonthValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gMonth value into an XML string representation.
- int [rtXmlEncGMonthDayValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gMonthDay value into an XML string representation.
- int [rtXmlEncGDayValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gDay value into an XML string representation.
- int [rtXmlEncHexBinary](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD hexBinary type.
- int [rtXmlEncHexBinaryAttr](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD hexBinary type as an attribute.
- int [rtXmlEncHexStrValue](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *data)
This function encodes a variable of the XSD hexBinary type.
- int [rtXmlEncIndent](#) (OSCTXT *pctxt)
This function adds indentation whitespace to the output stream.
- int [rtXmlEncInt](#) (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncIntValue](#) (OSCTXT *pctxt, OSINT32 value)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncIntAttr](#) (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD integer type as an attribute (name="value").
- int [rtXmlEncIntPattern](#) (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSUTF8CHAR *pattern)
This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.
- int [rtXmlEncInt64](#) (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncInt64Value](#) (OSCTXT *pctxt, OSINT64 value)

This function encodes a variable of the XSD integer type.

- int [rtXmlEncInt64Attr](#) (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *attrName, size_t attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").

- int [rtXmlEncNamedBits](#) (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSUINT32 nbits, const OSOCTET *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 BIT STRING type.

- int [rtXmlEncNSAttrs](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes namespace declaration attributes at the beginning of an XML document.

- int [rtXmlPrintNSAttrs](#) (const char *name, const OSRTDList *data)

This function prints a list of namespace attributes.

- int [rtXmlEncReal10](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 REAL base 10 type.

- int [rtXmlEncSoapArrayTypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value, size_t itemCount)

This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.

- int [rtXmlEncStartDocument](#) (OSCTXT *pctxt)

This function encodes the XML header text at the beginning of an XML document.

- int [rtXmlEncBOM](#) (OSCTXT *pctxt)

This function encodes the Unicode byte order mark header at the start of the document.

- int [rtXmlEncStartElement](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes a start element tag value (<elemName>).

- int [rtXmlEncStartSoapEnv](#) (OSCTXT *pctxt)

This function encodes a SOAP envelope start element tag.

- int [rtXmlEncStartSoapElems](#) (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)

This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag.

- int [rtXmlEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pxmlstr, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD string type.

- int [rtXmlEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)

This function encodes a variable of the XSD string type.

- int [rtXmlEncStringValue2](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, size_t valueLen)

This function encodes a variable of the XSD string type.

- int [rtXmlEncTermStartElement](#) (OSCTXT *pctxt)

This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator.
- int [rtXmlEncUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR *value, OSUINT32 nchars, const OS-UTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a Unicode string value.
- int [rtXmlEncUTF8Attr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value)

This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.
- int [rtXmlEncUTF8Attr2](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, size_t nameLen, const OS-UTF8CHAR *value, size_t valueLen)

This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.
- int [rtXmlEncUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OS-XMLNamespace *pNS)

This function encodes a UTF-8 string value.
- int [rtXmlEncUInt](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntValue](#) (OSCTXT *pctxt, OSUINT32 value)

This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntAttr](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *attrName, size_t attrName-
Len)

This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").
- int [rtXmlEncUInt64](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *elemName, OSXMLNames-
pace *pNS)

This function encodes a variable of the XSD integer type.
- int [rtXmlEncUInt64Value](#) (OSCTXT *pctxt, OSUINT64 value)

This function encodes a variable of the XSD integer type.
- int [rtXmlEncUInt64Attr](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *attrName, size_t attr-
NameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").
- int [rtXmlEncXSIAttrs](#) (OSCTXT *pctxt, OSBOOL needXSI)

This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.
- int [rtXmlEncXSITypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="value").
- int [rtXmlFreeInputSource](#) (OSCTXT *pctxt)

This function closes an input source that was previously created with one of the create input source functions such as 'rtXmlCreateFileInputSource'.
- int [rtXmlSetEncBufPtr](#) (OSCTXT *pctxt, OSOCTET *bufaddr, size_t bufsiz)

This function is used to set the internal buffer within the run-time library encoding context.

- int `rtXmlGetIndent` (OSCTXT *pctxt)
This function returns current XML output indent value.
- OSBOOL `rtXmlGetWriteBOM` (OSCTXT *pctxt)
This function returns whether the Unicode byte order mark will be encoded.
- int `rtXmlGetIndentChar` (OSCTXT *pctxt)
This function returns current XML output indent character value (default is space).

5.2.1 Define Documentation

5.2.1.1 #define `rtXmlGetEncBufLen(pctxt)` (pctxt) → `buffer.byteIndex`

This macro returns the length of the encoded XML message.

Parameters:

pctxt Pointer to a context structure.

Definition at line 2355 of file osrxml.h.

5.2.1.2 #define `rtXmlGetEncBufPtr(pctxt)` (pctxt) → `buffer.data`

This macro returns the start address of the encoded XML message.

If a static buffer was used, this is simply the start address of the buffer. If dynamic encoding was done, this will return the start address of the dynamic buffer allocated by the encoder.

Parameters:

pctxt Pointer to a context structure.

Definition at line 2348 of file osrxml.h.

5.2.2 Function Documentation

5.2.2.1 int `rtXmlEncAny` (OSCTXT *pctxt, OSXMLSTRING *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD any type.

This is considered to be a fully-wrapped element of any type (for example: <myType>myData</myType>)

Parameters:

pctxt Pointer to context block structure.

pvalue Value to be encoded. This is a string containing the fully-encoded XML text to be copied to the output stream.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.2 int rtXmlEncAnyAttr (OSCTXT * *pctxt*, OSRTDList * *pAnyAttrList*)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.

Parameters:

pctxt Pointer to context block structure.

pAnyAttrList List of attributes.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.3 int rtXmlEncAnyTypeValue (OSCTXT * *pctxt*, const OSUTF8CHAR * *pvalue*)

This function encodes a variable of the XSD anyType type.

This is considered to be a fully-wrapped element of any type, possibly containing attributes. (for example: * <myType>myData</myType>)

Parameters:

pctxt Pointer to context block structure.

pvalue Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.4 int rtXmlEncBase64Binary (OSCTXT * *pctxt*, OSUINT32 *noct*, const OSOCTET * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD base64Binary type.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.5 int rtXmlEncBase64BinaryAttr (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*)

This function encodes a variable of the XSD base64Binary type as an attribute.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length in bytes of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.6 int rtXmlEncBase64StrValue (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *value*)

This function encodes a variable of the XSD base64Binary type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.7 `int rtXmlEncBigInt (OSCTXT * pctxt, const OSUTF8CHAR * value, const OSUTF8CHAR * elemName, OSXMLNamespace * pNS)`

This function encodes a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

Items of this type are stored in character string constant variables. They can be represented as decimal strings (with no prefixes), as hexadecimal strings starting with a "0x" prefix, as octal strings starting with a "0o" prefix or as binary strings starting with a "0b" prefix. Other radices are currently not supported.

Parameters:

pctxt Pointer to context block structure.

value A pointer to a character string containing the value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.8 `int rtXmlEncBigIntAttr (OSCTXT * pctxt, const OSUTF8CHAR * value, const OSUTF8CHAR * attrName, size_t attrNameLen)`

This function encodes an XSD integer attribute value.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits).

Parameters:

pctxt Pointer to context block structure.

value A pointer to a character string containing the value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length in bytes of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.9 `int rtXmlEncBigIntValue (OSCTXT * pctxt, const OSUTF8CHAR * value)`

This function encodes an XSD integer attribute value.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). This function just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value A pointer to a character string containing the value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.10 int rtXmlEncBinStrValue (OSCTXT * *pctxt*, OSUINT32 *nbits*, const OSOCTET * *data*)

This function encodes a binary string value as a sequence of '1's and '0's.

Parameters:

pctxt Pointer to context block structure.

nbits Number of bits in the value string.

data Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.11 int rtXmlEncBitString (OSCTXT * *pctxt*, OSUINT32 *nbits*, const OSOCTET * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the ASN.1 BIT STRING type.

The encoded data is a sequence of '1's and '0's. This is only used if named bits are not specified in the string (

See also:

[rtXmlEncNamedBits](#)).

Parameters:

pctxt Pointer to context block structure.

nbits Number of bits in the bit string.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.12 **int rtXmlEncBOM (OSCTXT * *pctxt*)**

This function encodes the Unicode byte order mark header at the start of the document. It is called by `rtXmlEncStartDocument` and does not need to be called manually.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.13 **int rtXmlEncBool (OSCTXT * *pctxt*, OSBOOL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)**

This function encodes a variable of the XSD boolean type.

Parameters:

pctxt Pointer to context block structure.

value Boolean value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.14 **int rtXmlEncBoolAttr (OSCTXT * *pctxt*, OSBOOL *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*)**

This function encodes an XSD boolean attribute value.

Parameters:

pctxt Pointer to context block structure.

value Boolean value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length in bytes of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.15 int rtXmlEncBoolValue (OSCTXT * *pctxt*, OSBOOL *value*)

This function encodes a variable of the XSD boolean type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Boolean value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.16 int rtXmlEncDate (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD 'date' type as a string.

This version of the function is used to encode an OSXSDDateTime value into CCYY-MM-DD format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.17 int rtXmlEncDateTime (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric date/time value into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.18 int rtXmlEncDateTimeValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a numeric date/time value into an XML string representation.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.19 int rtXmlEncDateValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a variable of the XSD 'date' type as a string.

This version of the function is used to encode an OSXSDDateTime value into CCYY-MM-DD format. This function just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.20 int rtXmlEncDecimal (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDecimalFmt * *pFmtSpec*)

This function encodes a variable of the XSD decimal type.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.21 int rtXmlEncDecimalAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*, const OSDecimalFmt * *pFmtSpec*)

This function encodes a variable of the XSD decimal type as an attribute.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.22 int rtXmlEncDecimalValue (OSCTXT * *pctxt*, OSREAL *value*, const OSDecimalFmt * *pFmtSpec*, char * *pDestBuf*, size_t *destBufSize*)

This function encodes a value of the XSD decimal type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

pFmtSpec Pointer to format specification structure.

pDestBuf Pointer to a destination buffer. If NULL (*destBufSize* should be 0) the encoded value will be put in *pctxt->buffer* or in stream associated with the *pctxt*.

destBufSize The size of the destination buffer. Must be 0, if *pDestBuf* is NULL.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.23 int rtXmlEncDouble (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD double type.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.24 int rtXmlEncDoubleAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD double type as an attribute.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.25 int rtXmlEncDoubleValue (OSCTXT * *pctxt*, OSREAL *value*, const OSDoubleFmt * *pFmtSpec*, int *defaultPrecision*)

This function encodes a value of the XSD double or float type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

pFmtSpec Pointer to format specification structure.

defaultPrecision Default precision of the value. For float, it is 6, for double it is 15.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.26 int rtXmlEncEmptyElement (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*, OSBOOL *terminate*)

This function encodes an empty element tag value (<elemName/>).

Parameters:

pctxt Pointer to context block structure.

elemName XML element name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

terminate Add closing '>' character.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.27 int rtXmlEncEndDocument (OSCTXT * *pctxt*)

This function adds trailer information and a null terminator at the end of the XML document being encoded.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.28 int rtXmlEncEndElement (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes an end element tag value (</elemName>).

Parameters:

- pctxt* Pointer to context block structure.
- elemName* XML element name.
- pNS* XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.29 int rtXmlEncEndSoapElems (OSCTXT * *pctxt*, OSXMLSOAPMsgType *msgtype*)

This function encodes SOAP end element tags.

It will add a SOAP body or fault end tag based on the SOAP message type argument. It will then add an envelope end element tag.

Parameters:

- pctxt* Pointer to context block structure.
- msgtype* SOAP message type (body, fault, or none)

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.30 int rtXmlEncEndSoapEnv (OSCTXT * *pctxt*)

This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).

Parameters:

- pctxt* Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.31 int rtXmlEncFloat (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD float type.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.32 int rtXmlEncFloatAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD float type as an attribute.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.33 int rtXmlEncGDay (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gDay element into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.34 int rtXmlEncGDayValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a numeric gDay value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.35 int rtXmlEncGMonth (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gMonth element into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.36 int rtXmlEncGMonthDay (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gMonthDay element into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.37 int rtXmlEncGMonthDayValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a numeric gMonthDay value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.38 int rtXmlEncGMonthValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a numeric gMonth value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.39 int rtXmlEncGYear (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gYear element into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.40 int rtXmlEncGYearMonth (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gYearMonth element into an XML string representation.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.41 int rtXmlEncGYearMonthValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a numeric gYearMonth value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.42 `int rtXmlEncGYearValue (OSCTXT * pctxt, const OSXSDDateTime * pvalue)`

This function encodes a numeric gYear value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.43 `int rtXmlEncHexBinary (OSCTXT * pctxt, OSUINT32 nocts, const OSOCTET * value, const OSUTF8CHAR * elemName, OSXMLNamespace * pNS)`

This function encodes a variable of the XSD hexBinary type.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.44 `int rtXmlEncHexBinaryAttr (OSCTXT * pctxt, OSUINT32 nocts, const OSOCTET * value, const OSUTF8CHAR * attrName, size_t attrNameLen)`

This function encodes a variable of the XSD hexBinary type as an attribute.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.45 int rtXmlEncHexStrValue (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *data*)

This function encodes a variable of the XSD hexBinary type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

data Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.46 int rtXmlEncIndent (OSCTXT * *pctxt*)

This function adds indentation whitespace to the output stream.

The amount of indentation to add is determined by the level member variable in the context structure and the OSXML-LINDENT constant value.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.47 int rtXmlEncInt (OSCTXT * *pctxt*, OSINT32 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD integer type.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.48 int rtXmlEncInt64 (OSCTXT * *pctxt*, OSINT64 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD integer type.

This version of the function is used for 64-bit integer values.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.49 int rtXmlEncInt64Attr (OSCTXT * *pctxt*, OSINT64 *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*)

This function encodes a variable of the XSD integer type as an attribute (name="value").

This version of the function is used for 64-bit integer values.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.50 **int rtXmlEncInt64Value (OSCTXT * *pctxt*, OSINT64 *value*)**

This function encodes a variable of the XSD integer type.

This version of the function is used for 64-bit integer values. It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.51 **int rtXmlEncIntAttr (OSCTXT * *pctxt*, OSINT32 *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*)**

This function encodes a variable of the XSD integer type as an attribute (name="value").

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.52 **int rtXmlEncIntPattern (OSCTXT * *pctxt*, OSINT32 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSUTF8CHAR * *pattern*)**

This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

pattern Pattern of the encoded value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.53 int rtXmlEncIntValue (OSCTXT * *pctxt*, OSINT32 *value*)

This function encodes a variable of the XSD integer type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.54 int rtXmlEncNamedBits (OSCTXT * *pctxt*, const OSBitMapItem * *pBitMap*, OSUINT32 *nbits*, const OSOCTET * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the ASN.1 BIT STRING type.

In this case, a set of named bits was provided in the schema for the bit values. The encoding is a list of the named bit identifiers corresponding to each set bit in the bit string value.

Parameters:

pctxt Pointer to context block structure.

pBitMap Bit map equating symbolic bit names to bit numbers.

nbits Number of bits in the bit string value.

pvalue Bit string value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.55 **int rtXmlEncNSAttrs (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)**

This function encodes namespace declaration attributes at the beginning of an XML document.

The attributes to be encoded are stored in the namespace list provided, or within the context if a NULL pointer is passed for *pNSAttrs*. Namespaces are added to this list by using the namespace utility functions.

Parameters:

- pctxt* Pointer to context block structure.
- pNSAttrs* Pointer to list of namespace attributes.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.56 **int rtXmlEncReal10 (OSCTXT * *pctxt*, const OSUTF8CHAR * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)**

This function encodes a variable of the ASN.1 REAL base 10 type.

Parameters:

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- pvalue* A pointer to an REAL base 10 value.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 (0) = success,
- negative return value is error.

5.2.2.57 **int rtXmlEncSoapArrayTypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *name*, const OSUTF8CHAR * *value*, size_t *itemCount*)**

This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.

The form of this attribute is 'attrType="<type>[count]"'.

Parameters:

- pctxt* Pointer to context block structure.
- name* Attribute name (NS prefix + arrayType)
- value* UTF-8 string value to be encoded.

itemCount Count of the number of elements in the array.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.58 int rtXmlEncStartDocument (OSCTXT * *pctxt*)

This function encodes the XML header text at the beginning of an XML document.

This is normally the following:

```
<?xml version="1.0" encoding="UTF-8"?>
```

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.59 int rtXmlEncStartElement (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*, OSBOOL *terminate*)

This function encodes a start element tag value (<*elemName*>).

Parameters:

pctxt Pointer to context block structure.

elemName XML element name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

terminate Add closing '>' character.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.60 `int rtXmlEncStartSoapElems (OSCTXT * pctxt, OSXMLSOAPMsgType msgtype)`

This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag. This includes all of the standard SOAP namespace attributes.

Parameters:

- pctxt* Pointer to context block structure.
- msgtype* SOAP message type (body, fault, or none)

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.61 `int rtXmlEncStartSoapEnv (OSCTXT * pctxt)`

This function encodes a SOAP envelope start element tag. This includes all of the standard SOAP namespace attributes.

Parameters:

- pctxt* Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.62 `int rtXmlEncString (OSCTXT * pctxt, OSXMLSTRING * pxmlstr, const OSUTF8CHAR * elemName, OSXMLNamespace * pNS)`

This function encodes a variable of the XSD string type.

Parameters:

- pctxt* Pointer to context block structure.
- pxmlstr* XML string value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.63 `int rtXmlEncStringValue (OSCTXT * pctxt, const OSUTF8CHAR * value)`

This function encodes a variable of the XSD string type.

Parameters:

- pctxt* Pointer to context block structure.
- value* XML string value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.64 `int rtXmlEncStringValue2 (OSCTXT * pctxt, const OSUTF8CHAR * value, size_t valueLen)`

This function encodes a variable of the XSD string type.

Parameters:

- pctxt* Pointer to context block structure.
- value* XML string value to be encoded.
- valueLen* UTF-8 string value length (in octets).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.65 `int rtXmlEncTermStartElement (OSCTXT * pctxt)`

This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator. It will also add XSI attributes to the element.

Parameters:

- pctxt* Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.66 int rtXmlEncTime (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD 'time' type as a string.

This version of the function is used to encode OSXSDDateTime value into any of following format in different condition as stated below. (1) hh-mm-ss.ss used if *tz_flag* = false (2) hh-mm-ss.ssZ used if *tz_flag* = false and *tzo* = 0 (3) hh-mm-ss.ss+HH:MM if *tz_flag* = false and *tzo* > 0 (4) hh-mm-ss.ss-HH:MM-HH:MM if *tz_flag* = false and *tzo* < 0

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.67 int rtXmlEncTimeValue (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*)

This function encodes a variable of the XSD 'time' type as a string.

This version of the function just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.68 int rtXmlEncUInt (OSCTXT * *pctxt*, OSUINT32 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD unsigned integer type.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.69 int rtXmlEncUInt64 (OSCTXT * *pctxt*, OSUINT64 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD integer type.

This version of the function is used when constraints cause an unsigned 64-bit integer variable to be used.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.70 int rtXmlEncUInt64Attr (OSCTXT * *pctxt*, OSUINT64 *value*, const OSUTF8CHAR * *attrName*, size_t *attrNameLen*)

This function encodes a variable of the XSD integer type as an attribute (name="value").

This version of the function is used for unsigned 64-bit integer values.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.71 `int rtXmlEncUInt64Value (OSCTXT * pctxt, OSUINT64 value)`

This function encodes a variable of the XSD integer type.

This version of the function is used when constraints cause an unsigned 64-bit integer variable to be used. It writes the encoded value to the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.72 `int rtXmlEncUIntAttr (OSCTXT * pctxt, OSUINT32 value, const OSUTF8CHAR * attrName, size_t attrNameLen)`

This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.73 `int rtXmlEncUIntValue (OSCTXT * pctxt, OSUINT32 value)`

This function encodes a variable of the XSD unsigned integer type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.74 `int rtXmlEncUnicodeStr (OSCTXT * pctxt, const OSUNICHAR * value, OSUINT32 nchars, const OSUTF8CHAR * elemName, OSXMLNamespace * pNS)`

This function encodes a Unicode string value.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded. This is a pointer to an array of 16-bit integer values.

nchars Number of characters in value array.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.75 `int rtXmlEncUTF8Attr (OSCTXT * pctxt, const OSUTF8CHAR * name, const OSUTF8CHAR * value)`

This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.

Parameters:

pctxt Pointer to context block structure.

name Attribute name.

value UTF-8 string value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.76 `int rtXmlEncUTF8Attr2 (OSCTXT * pctxt, const OSUTF8CHAR * name, size_t nameLen, const OSUTF8CHAR * value, size_t valueLen)`

This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.

Parameters:

pctxt Pointer to context block structure.

name Attribute name.

nameLen Attribute name length (in octets).

value UTF-8 string value to be encoded.

valueLen UTF-8 string value length (in octets).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.77 `int rtXmlEncUTF8Str (OSCTXT * pctxt, const OSUTF8CHAR * value, const OSUTF8CHAR * elemName, OSXMLNamespace * pNS)`

This function encodes a UTF-8 string value.

Parameters:

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.78 `int rtXmlEncXSIAttrs (OSCTXT * pctxt, OSBOOL needXSI)`

This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.

The encoded attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

The XSI namespace declaration will only be added to the document if schema location attributes exist or the 'needXSI' flag (see below) is set.

Parameters:

pctxt Pointer to context block structure.

needXSI This flag is set to true to indicate the XSI namespace declaration is required to support XML items in the main document body such as `xsi:type` or `xsi:nil`.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.79 `int rtXmlEncXSITypeAttr (OSCTXT * pctxt, const OSUTF8CHAR * value)`

This function encodes an XML schema instance (XSI) type attribute value (`xsi:type="value"`).

Parameters:

pctxt Pointer to context block structure.

value XSI type attribute value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.80 `int rtXmlFreeInputSource (OSCTXT * pctxt)`

This function closes an input source that was previously created with one of the create input source functions such as `'rtXmlCreateFileInputSource'`.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.81 `int rtXmlGetIndent (OSCTXT * pctxt)`

This function returns current XML output indent value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

Current indent value (≥ 0) if OK, negative status code if error.

5.2.2.82 `int rtXmlGetIndentChar (OSCTXT * pctxt)`

This function returns current XML output indent character value (default is space).

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

Current indent character (> 0) if OK, negative status code if error.

5.2.2.83 OSBOOL rtXmlGetWriteBOM (OSCTXT * *pctxt*)

This function returns whether the Unicode byte order mark will be encoded.

Parameters:

pctxt Pointer to OSCTXT structure.

Returns:

TRUE if BOM is to be encoded, FALSE if not or if context uninitialized.

5.2.2.84 int rtXmlPrintNSAttrs (const char * *name*, const OSRTDList * *data*)

This function prints a list of namespace attributes.

Parameters:

name Name to print.

data List of namespace attributes.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.2.2.85 int rtXmlSetEncBufPtr (OSCTXT * *pctxt*, OSOCTET * *bufaddr*, size_t *bufsiz*)

This function is used to set the internal buffer within the run-time library encoding context.

It must be called after the context variable is initialized by the rtxInitContext function and before any other compiler generated or run-time library encode function.

Parameters:

pctxt Pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

bufaddr A pointer to a memory buffer to use to encode a message. The buffer should be declared as an array of unsigned characters (OCTETs). This parameter can be set to NULL to specify dynamic encoding (i.e., the encode functions will dynamically allocate a buffer to hold the encoded message).

bufsiz The length of the memory buffer in bytes. Should be set to zero if NULL was specified for *bufaddr* (i.e. dynamic encoding was selected).

5.3 XML utility functions.

Functions

- int [rtXmlWriteToFile](#) (OSCTXT *pctxt, const char *filename)

This function writes the encoded XML message stored in the context message buffer out to a file.

5.3.1 Function Documentation

5.3.1.1 int rtXmlWriteToFile (OSCTXT *pctxt, const char *filename)

This function writes the encoded XML message stored in the context message buffer out to a file.

Parameters:

pctxt Pointer to OSCTXT structure.

filename Full path to file to which XML is to be written.

Returns:

0 - if success, negative value if error.

5.4 XML pull-parser decode functions.

Functions

- int [rtXmlpDecAny](#) (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int [rtXmlpDecAnyAttrStr](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrStr, size_t index)
This function decodes an any attribute string.
- int [rtXmlpDecAnyElem](#) (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int [rtXmlpDecBase64Str](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocets, OSINT32 bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int [rtXmlpDecBigInt](#) (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function will decode a variable of the XSD integer type.
- int [rtXmlpDecBitString](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes a bit string value.
- int [rtXmlpDecBool](#) (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int [rtXmlpDecDate](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int [rtXmlpDecDateTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int [rtXmlpDecDecimal](#) (OSCTXT *pctxt, OSREAL *pvalue, int totalDigits, int fractionDigits)
This function decodes the contents of a decimal data type.
- int [rtXmlpDecDouble](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int [rtXmlpDecDynBase64Str](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int [rtXmlpDecDynBitString](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a bit string value.
- int [rtXmlpDecDynHexStr](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int [rtXmlpDecDynUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR **ppdata, OSUINT32 *pnchars)
This function decodes a Unicode string data type.
- int [rtXmlpDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)

This function decodes the contents of a UTF-8 string data type.

- int [rtXmlpDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *out, size_t max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlpDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlpDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlpDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlpDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlpDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlpDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlpDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlpDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlpDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlpDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int [rtXmlpDecNamedBits](#) (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes the contents of a named bit field.
- int [rtXmlpDecStrList](#) (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int [rtXmlpDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.
- int [rtXmlpDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.
- int [rtXmlpDecUInt8](#) (OSCTXT *pctxt, OSOCTET *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.

- int [rtXmlpDecUInt16](#) (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int [rtXmlpDecUInt64](#) (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.
- int [rtXmlpDecXmlStr](#) (OSCTXT *pctxt, OSXMLSTRING *outdata)
This function decodes the contents of an XML string data type.
- int [rtXmlpDecXmlStrList](#) (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int [rtXmlpDecXSIAttr](#) (OSCTXT *pctxt, const OSXMLNameFragments *attrName)
This function decodes XSI (XML Schema Instance) and XML namespace attributes that may be present in any arbitrary XML element within a document.
- int [rtXmlpDecXSITypeAttr](#) (OSCTXT *pctxt, const OSXMLNameFragments *attrName, const OS-UTF8CHAR **ppAttrValue)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int [rtXmlpGetAttributeID](#) (const OSXMLStrFragment *attrName, OSINT16 nsidx, size_t nAttr, const OSXMLAttrDescr attrNames[], OSUINT32 attrPresent[])
This function finds an attribute in the descriptor table.
- int [rtXmlpGetNextElem](#) (OSCTXT *pctxt, OSXMLElemDescr *pElem, OSINT32 level)
This function parse the next element start tag.
- int [rtXmlpGetNextElemID](#) (OSCTXT *pctxt, const OSXMLElemIDRec *tab, size_t nrows, OSINT32 level, OSBOOL continueParse)
This function parses the next start tag and finds the index of the element name in the descriptor table.
- int [rtXmlpMarkLastEventActive](#) (OSCTXT *pctxt)
This function marks current tag as unprocessed.
- int [rtXmlpMatchStartTag](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemLocalName, OSINT16 nsidx)
This function parses the next start tag that matches with given name.
- int [rtXmlpMatchEndTag](#) (OSCTXT *pctxt, OSINT32 level)
This function parse next end tag that matches with given name.
- OSBOOL [rtXmlpHasAttributes](#) (OSCTXT *pctxt)
This function checks accessibility of attributes.
- int [rtXmlpGetAttributeCount](#) (OSCTXT *pctxt)
This function returns number of attributes in last processed start tag.
- int [rtXmlpSelectAttribute](#) (OSCTXT *pctxt, OSXMLNameFragments *pAttr, OSINT16 *nsidx, size_t index)
This function selects attribute to decode.
- OSINT32 [rtXmlpGetCurrentLevel](#) (OSCTXT *pctxt)

This function returns current nesting level.

- void **rtXmlpSetWhiteSpaceMode** (OSCTXT *pctx, OSXMLWhiteSpaceMode whiteSpaceMode)
Sets the whitespace treatment mode.
- OSBOOL **rtXmlpSetMixedContentMode** (OSCTXT *pctx, OSBOOL mixedContentMode)
Sets mixed content mode.
- void **rtXmlpSetListMode** (OSCTXT *pctx)
Sets list mode.
- OSBOOL **rtXmlpListHasItem** (OSCTXT *pctx)
Check for end of decoded token list.
- void **rtXmlpCountListItems** (OSCTXT *pctx, OSUINT32 *itemCnt)
Count tokens in list.
- int **rtXmlpNextSeqElemID** (OSCTXT *pctx, const OSXMLElemIDRec *tab, const OSXMLGroupDesc *pGroup, int curID, int lastMandatoryID, OSBOOL groupMode)
This function parses the next start tag and find index of element name in descriptor table.
- int **rtXmlpNextAllElemID** (OSCTXT *pctx, const OSXMLElemIDRec *tab, size_t nRows, const OSUINT8 *pOrder, OSUINT32 nOrder, OSUINT32 maxOrder, int anyID)
This function parses the next start tag and finds index of element name in descriptor table.
- int **rtXmlpNextAllElemID16** (OSCTXT *pctx, const OSXMLElemIDRec *tab, size_t nRows, const OSUINT16 *pOrder, OSUINT32 nOrder, OSUINT32 maxOrder, int anyID)
This function parses the next start tag and finds index of element name in descriptor table.
- void **rtXmlpSetNamespaceTable** (OSCTXT *pctx, const OSUTF8CHAR *namespaceTable[], size_t nNamespaces)
Sets user namespace table.
- int **rtXmlpCreateReader** (OSCTXT *pctx)
Creates pull parser reader structure within the context.
- void **rtXmlpHideAttributes** (OSCTXT *pctx)
Disable access to attributes.
- OSBOOL **rtXmlpNeedDecodeAttributes** (OSCTXT *pctx)
This function checks if attributes were previously decoded.
- void **rtXmlpMarkPos** (OSCTXT *pctx)
Save current decode position.
- void **rtXmlpRewindToMarkedPos** (OSCTXT *pctx)
Rewind to saved decode position.
- void **rtXmlpResetMarkedPos** (OSCTXT *pctx)
Reset saved decode position.

- int [rtXmlpGetXSITypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrValue, OSINT16 *nsidx, size_t *pLocalOffs)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int [rtXmlpGetXmlnsAttrs](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs)
This function decodes namespace attributes from start tag and adds them to the given list.
- int [rtXmlpDecXSIAttrs](#) (OSCTXT *pctxt)
This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.
- OSBOOL [rtXmlpIsEmptyElement](#) (OSCTXT *pctxt)
Check element content: empty or not.
- int [rtXmlEncAttrC14N](#) (OSCTXT *pctxt)
This function used only in C14 mode.
- OSBOOL [rtXmlpIsLastEventDone](#) (OSCTXT *pctxt)
Check processing status of current tag.
- int [rtXmlpGetXSITypeIndex](#) (OSCTXT *pctxt, const OSXMLItemDescr typetab[], size_t typetabsiz)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.
- int [rtXmlpLookupXSITypeIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *pXsiType, OSINT16 xsiTypeIdx, const OSXMLItemDescr typetab[], size_t typetabsiz)
This function find index of XSI (XML Schema Instance) type in descriptor table.
- void [rtXmlpForceDecodeAsGroup](#) (OSCTXT *pctxt)
Disable skipping of unknown elements in optional sequence tail.
- OSBOOL [rtXmlpIsDecodeAsGroup](#) (OSCTXT *pctxt)
This function checks if "decode as group" mode was forced.
- OSBOOL [rtXmlpIsUTF8Encoding](#) (OSCTXT *pctxt)
This function checks if the encoding specified in XML header is UTF-8.

5.4.1 Function Documentation

5.4.1.1 int [rtXmlEncAttrC14N](#) (OSCTXT * *pctxt*)

This function used only in C14 mode.

It provide attributes sorting.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.2 void rtXmlpCountListItems (OSCTXT * *pctxt*, OSUINT32 * *itemCnt*)

Count tokens in list.

Parameters:

pctxt Pointer to context block structure.

itemCnt Pointer to number of elements in list.

Returns:

Token number. For element content function check accessed part of content only. Returned value may be below then real token number.

5.4.1.3 int rtXmlpCreateReader (OSCTXT * *pctxt*)

Creates pull parser reader structure within the context.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.4 int rtXmlpDecAny (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)

This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).

The decoded XML fragment is returned as a string in the form as it appears in the document. Memory is allocated for the string using the `rtxMemAlloc` function.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to UTF8 character string pointer to receive decoded XML fragment. Memory is allocated for the string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.5 **int rtXmlpDecAnyAttrStr (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppAttrStr*, size_t *index*)**

This function decodes an any attribute string.

The full attribute string (name="value") is decoded and returned on the string output argument. Memory is allocated for the string using the `rtxMemAlloc` function.

Parameters:

pctxt Pointer to context block structure.

ppAttrStr Pointer to UTF8 character string pointer to receive decoded attribute string. Memory is allocated for the string using the run-time memory manager.

index Index of attribute.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.6 **int rtXmlpDecAnyElem (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)**

This function decodes an arbitrary XML section of code as defined by the XSD any type (`xsd:any`).

The decoded XML fragment is returned as a string in the form as it appears in the document. Memory is allocated for the string using the `rtxMemAlloc` function. The difference between this function and `rtXmlpDecAny` is that this function preserves the full encoded XML fragment including the start and end elements tags and attributes. `rtXmlpDecAny` decodes the contents within the start and end tags.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to UTF8 character string pointer to receive decoded XML fragment. Memory is allocated for the string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.7 **int rtXmlpDecBase64Str (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)**

This function decodes a contents of a Base64-encode binary string into a static memory structure.

The octet string must be Base64 encoded. This function call is used to decode a sized base64Binary string production. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.8 int rtXmlpDecBigInt (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)

This function will decode a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

These variables are stored in character string constant variables. The radix should be 10. If it is necessary to convert to another radix, then use `rtxBigIntSetStr` or `rtxBigIntToString` functions. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the `rtMemAlloc` function. The decoded variable is represented as a string starting with appropriate prefix.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.9 int rtXmlpDecBitString (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnbits*, OSUINT32 *bufsize*)

This function decodes a bit string value.

The string consists of a series of '1' and '0' characters. This is the static version in which the user provides a pre-allocated memory buffer to receive the decoded data. One byte in a memory buffer can hold 8 characters of encoded data. Bits are stored from MSB to LSB order.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

pnbits Pointer to hold decoded number of bits.

bufsize Size of buffer passed in *pvalue* argument.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.10 int rtXmlpDecBool (OSCTXT * *pctxt*, OSBOOL * *pvalue*)

This function decodes a variable of the boolean type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.11 int rtXmlpDecDate (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)

This function decodes a variable of the XSD 'date' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY-MM-DD format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.12 int rtXmlpDecDateTime (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)

This function decodes a variable of the XSD 'dateTime' type.

Input is expected to be a string of characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.13 int rtXmlpDecDecimal (OSCTXT * *pctxt*, OSREAL * *pvalue*, int *totalDigits*, int *fractionDigits*)

This function decodes the contents of a decimal data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

totalDigits Number of total digits in the decimal number from XSD totalDigits facet value. Argument should be set to -1 if facet not given.

fractionDigits Number of fraction digits in the decimal number from XSD fractionDigits facet value. Argument should be set to -1 if facet not given.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.14 int rtXmlpDecDouble (OSCTXT * *pctxt*, OSREAL * *pvalue*)

This function decodes the contents of a float or double data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.15 int rtXmlpDecDynBase64Str (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a Base64-encode binary string.

The octet string must be Base64 encoded. This function will allocate dynamic memory to store the decoded result. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated for the string using the `rtxMemAlloc` function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.16 int rtXmlpDecDynBitString (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a bit string value.

The string consists of a series of '1' and '0' characters. This is the dynamic version in which memory is allocated for the returned binary string variable. Bits are stored from MSB to LSB order.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.17 int rtXmlpDecDynHexStr (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a hexBinary string.

This function will allocate dynamic memory to store the decoded result. Input is expected to be a string of OS-UTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the `rtxMemAlloc` function.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.18 **int rtXmlpDecDynUnicodeStr (OSCTXT * *pctxt*, const OSUNICHAR ** *ppdata*, OSUINT32 * *pchars*)**

This function decodes a Unicode string data type.

The input is assumed to be in UTF-8 format. This function reads each character and converts it into its Unicode equivalent.

Parameters:

pctxt Pointer to context block structure.

ppdata Pointer to Unicode character string. A Unicode character string is represented as an array of unsigned 16-bit integers in C. Memory is allocated for the string using the run-time memory manager.

pchars Pointer to integer variables to receive the number of characters in the string.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.19 **int rtXmlpDecDynUTF8Str (OSCTXT * *pctxt*, const OSUTF8CHAR ** *outdata*)**

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

outdata Pointer to a pointer to receive decoded UTF-8 string. Memory is allocated for this string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.20 **int rtXmlpDecGDay (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gDay' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have —DD[-+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.21 **int rtXmlpDecGMonth (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gMonth' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have –MM[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.22 **int rtXmlpDecGMonthDay (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gMonthDay' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have –MM-DD[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.23 **int rtXmlpDecGYear (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)**

This function decodes a variable of the XSD 'gYear' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY[+hh:mm|Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.24 int rtXmlpDecGYearMonth (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)

This function decodes a variable of the XSD 'gYearMonth' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY-MM[-hh:mm][Z] format.

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.25 int rtXmlpDecHexStr (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)

This function decodes the contents of a hexBinary string into a static memory structure.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.26 `int rtXmlpDecInt (OSCTXT * pctxt, OSINT32 * pvalue)`

This function decodes the contents of a 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 32-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.27 `int rtXmlpDecInt16 (OSCTXT * pctxt, OSINT16 * pvalue)`

This function decodes the contents of a 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 16-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.28 `int rtXmlpDecInt64 (OSCTXT * pctxt, OSINT64 * pvalue)`

This function decodes the contents of a 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.29 `int rtXmlpDecInt8 (OSCTXT * pctxt, OSINT8 * pvalue)`

This function decodes the contents of an 8-bit integer data type (i.e.

a signed byte type in the range of -128 to 127). Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to 8-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.30 `int rtXmlpDecNamedBits (OSCTXT * pctxt, const OSBitMapItem * pBitMap, OSOCTET * pvalue, OSUINT32 * pnbits, OSUINT32 bufsize)`

This function decodes the contents of a named bit field.

This is a space-separated list of token values in which each token corresponds to a bit field in a bit map.

Parameters:

pctxt Pointer to context block structure.

pBitMap Pointer to bit map structure that defined token to bit mappings.

pvalue Pointer to buffer to receive decoded bit map.

pnbits Number of bits in decoded bit map.

bufsize Size of buffer passed in to receive decoded bit values.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.31 `int rtXmlpDecStrList (OSCTXT * pctxt, OSRTDList * plist)`

This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.

Memory is allocated for the list nodes and token values using the rtx memory management functions.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

plist A pointer to a linked list structure to which the parsed token values will be added.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.32 int rtXmlpDecTime (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)

This function decodes a variable of the XSD 'time' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have one of following formats:

(1) hh-mm-ss.ss used if *tz_flag* = false (2) hh-mm-ss.ssZ used if *tz_flag* = false and *tzo* = 0 (3) hh-mm-ss.ss+HH:MM if *tz_flag* = false and *tzo* > 0 (4) hh-mm-ss.ss-HH:MM-HH:MM if *tz_flag* = false and *tzo* < 0

Parameters:

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.33 int rtXmlpDecUInt (OSCTXT * *pctxt*, OSUINT32 * *pvalue*)

This function decodes the contents of an unsigned 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 32-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.34 int rtXmlpDecUInt16 (OSCTXT * *pctxt*, OSUINT16 * *pvalue*)

This function decodes the contents of an unsigned 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 16-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.35 int rtXmlpDecUInt64 (OSCTXT * *pctxt*, OSUINT64 * *pvalue*)

This function decodes the contents of an unsigned 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 64-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.36 int rtXmlpDecUInt8 (OSCTXT * *pctxt*, OSOCTET * *pvalue*)

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

a signed byte type in the range of 0 to 255). Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 8-bit integer value to receive decoded result.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.37 int rtXmlpDecUTF8Str (OSCTXT * *pctxt*, OSUTF8CHAR * *out*, size_t *max_len*)

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters:

pctxt Pointer to context block structure.

out Pointer to an array of OSUTF8CHAR to receive decoded UTF-8 string.

max_len Length of out array.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.38 int rtXmlpDecXmlStr (OSCTXT * *pctxt*, OSXMLSTRING * *outdata*)

This function decodes the contents of an XML string data type.

This type contains a pointer to a UTF-8 character string plus flags that can be set to alter the encoding of the string (for example, the cdata flag allows the string to be encoded in a CDATA section). Input is expected to be a string of UTF-8 characters returned by an XML parser.

Parameters:

pctxt Pointer to context block structure.

outdata Pointer to an XML string structure to receive the decoded string. Memory is allocated for the string using the run-time memory manager.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.39 int rtXmlpDecXmlStrList (OSCTXT * *pctxt*, OSRTDList * *plist*)

This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.

Memory is allocated for the list nodes and token values using the rtx memory management functions. List contains OSXMLSTRING structures.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

plist A pointer to a linked list structure to which the parsed token values will be added.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.40 `int rtXmlpDecXSIAttr (OSCTXT * pctxt, const OSXMLNameFragments * attrName)`

This function decodes XSI (XML Schema Instance) and XML namespace attributes that may be present in any arbitrary XML element within a document.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

attrName A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.41 `int rtXmlpDecXSIAattrs (OSCTXT * pctxt)`

This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.42 `int rtXmlpDecXSITypeAttr (OSCTXT * pctxt, const OSXMLNameFragments * attrName, const OSUTF8CHAR ** ppAttrValue)`

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

attrName A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

ppAttrValue A pointer to a pointer to a UTF8 character string to received the decoded XSI type name.

Returns:

Completion status of operation:

- 0 = success,
- 1 = OK, but *attrName* was not `xsi:type` (i.e. no attribute match)
- negative return value is error.

5.4.1.43 void rtXmlpForceDecodeAsGroup (OSCTXT * *pctxt*)

Disable skipping of unknown elements in optional sequence tail.

Function used in outer types to break decode on first unknown element after decoding mandatory sequence part.

Parameters:

pctxt Pointer to context block structure.

5.4.1.44 int rtXmlpGetAttributeCount (OSCTXT * *pctxt*)

This function returns number of attributes in last processed start tag.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- zero or positive value is attributes number,
- negative return value is error.

5.4.1.45 int rtXmlpGetAttributeID (const OSXMLStrFragment * *attrName*, OSINT16 *nsidx*, size_t *nAttr*, const OSXMLAttrDescr *attrNames*[], OSUINT32 *attrPresent*[])

This function finds an attribute in the descriptor table.

Parameters:

attrName A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

nsidx Namespace index:

- 0 = attribute is unqualified,
- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect.

nAttr Number of descriptors in table.

attrNames Attributes descriptor table.

attrPresent Bit array to mark already decoded attributes. It is used to identify duplicate attributes.

Returns:

Completion status of operation:

- positive or zero return value is attribute index in descriptor table,
- negative return value is error.

5.4.1.46 OSINT32 rtXmlpGetCurrentLevel (OSCTXT * *pctxt*)

This function returns current nesting level.

Parameters:

pctxt Pointer to context block structure.

Returns:

Current nesting level.

5.4.1.47 int rtXmlpGetNextAllElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, size_t *nrows*, const OSUINT8 * *pOrder*, OSUINT32 *nOrder*, OSUINT32 *maxOrder*, int *anyID*)

This function parses the next start tag and finds index of element name in descriptor table.

It used for decode "all" content model in strict mode.

Parameters:

pctxt Pointer to context block structure.

tab Elements descriptor table.

nrows Number of descriptors in table.

pOrder Pointer to array to receive elements order.

nOrder Last element's index in order array.

maxOrder Size of order array.

anyID Identifier of xsd:any element.

Returns:

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

5.4.1.48 int rtXmlpGetNextAllElemID16 (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, size_t *nrows*, const OSUINT16 * *pOrder*, OSUINT32 *nOrder*, OSUINT32 *maxOrder*, int *anyID*)

This function parses the next start tag and finds index of element name in descriptor table.

It used for decode "all" content model in strict mode. This variant used when xsd:all has above 256 elements.

Parameters:

pctxt Pointer to context block structure.

tab Elements descriptor table.

nrows Number of descriptors in table.

pOrder Pointer to array to receive elements order.

nOrder Last element's index in order array.

maxOrder Size of order array.

anyID Identifier of xsd:any element.

Returns:

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

5.4.1.49 int rtXmlpGetNextElem (OSCTXT * *pctxt*, OSXMLElemDescr * *pElem*, OSINT32 *level*)

This function parse the next element start tag.

Parameters:

pctxt Pointer to context block structure.

pElem Pointer to a structure to receive the decoded element descriptor.

level Nesting level of parsed start tag. When value equal -1 parsed next start tag.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.50 int rtXmlpGetNextElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, size_t *nrows*, OSINT32 *level*, OSBOOL *continueParse*)

This function parses the next start tag and finds the index of the element name in the descriptor table.

Parameters:

pctxt Pointer to context block structure.

tab Elements descriptor table.

nrows Number of descriptors in table.

level Nesting level of parsed start tag. When value equal -1 function parse next start tag.

continueParse When value equals TRUE function skips unrecognized elements.

Returns:

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

5.4.1.51 int rtXmlpGetNextSeqElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, const OSXMLGroupDesc * *pGroup*, int *curID*, int *lastMandatoryID*, OSBOOL *groupMode*)

This function parses the next start tag and find index of element name in descriptor table.

It is used to decode sequences in strict mode.

Parameters:

pctxt Pointer to context block structure.

tab Elements descriptor table.

pGroup Decode groups table.

curID Current decode group.

lastMandatoryID Identifier of last mandatory element.

groupMode This parameter must be setted to TRUE when decode groups or base types.

Returns:

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

5.4.1.52 int rtXmlpGetXmlnsAttrs (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function decodes namespace attributes from start tag and adds them to the given list.

Parameters:

pctxt Pointer to context block structure.

pNSAttrs A pointer to a linked list of OSXMLNamespace structures.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.53 int rtXmlpGetXSITypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppAttrValue*, OSINT16 * *nsidx*, size_t * *pLocalOffs*)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).

Parameters:

pctxt Pointer to context block structure.

ppAttrValue A pointer to a pointer to a UTF8 character string to received the decoded XSI type QName.

nsidx A pointer to OSINT16 value to received the decoded XSI type namespace index.

pLocalOffs A pointer to size_t value to received the local name offset in *ppAttrValue*. When *pLocalOffs* value equal NULL function return in *ppAttrValue* local name only.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.54 int rtXmlpGetXSITypeIndex (OSCTXT * *pctxt*, const OSXMLItemDescr *typetab*[], size_t *typetabsiz*)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.

Parameters:

pctxt Pointer to context block structure.

typetab XSI types descriptor table.

typetabsiz Number of descriptors in table.

Returns:

Completion status of operation:

- positive or zero value is type index,
- negative return value is error.

5.4.1.55 OSBOOL rtXmlpHasAttributes (OSCTXT * *pctxt*)

This function checks accessibility of attributes.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- TRUE = attributes are present and access is enabled,
- FALSE = attributes are absent or access is disabled.

5.4.1.56 void rtXmlpHideAttributes (OSCTXT * *pctxt*)

Disable access to attributes.

Function used in derived types to disable repeated decode in base type.

Parameters:

pctxt Pointer to context block structure.

5.4.1.57 OSBOOL rtXmlpIsDecodeAsGroup (OSCTXT * *pctxt*)

This function checks if "decode as group" mode was forced.

Parameters:

pctxt Pointer to context block structure.

Returns:

State of mode:

- TRUE = need decode as group,
- FALSE = normal sequence decoding.

5.4.1.58 OSBOOL rtXmlpIsEmptyElement (OSCTXT * *pctxt*)

Check element content: empty or not.

Parameters:

pctxt Pointer to context block structure.

Returns:

Status of element content:

- TRUE = element is empty,
- FALSE = element has content.

5.4.1.59 OSBOOL rtXmlpIsLastEventDone (OSCTXT * *pctxt*)

Check processing status of current tag.

Parameters:

pctxt Pointer to context block structure.

Returns:

Status of element content:

- TRUE = tag marked as processed,
- FALSE = tag will be processed again.

5.4.1.60 OSBOOL rtXmlpIsUTF8Encoding (OSCTXT * *pctxt*)

This function checks if the encoding specified in XML header is UTF-8.

Parameters:

pctxt Pointer to context block structure.

Returns:

State of mode:

- TRUE = is in UTF-8 encoding,
- FALSE = is not in UTF-8 encoding.

5.4.1.61 OSBOOL rtXmlpListHasItem (OSCTXT * *pctxt*)

Check for end of decoded token list.

Parameters:

pctxt Pointer to context block structure.

Returns:

State of decoded list:

- TRUE = list is not finished,
- FALSE = all tokens was decoded.

5.4.1.62 int rtXmlpLookupXSITypeIndex (OSCTXT * *pctxt*, const OSUTF8CHAR * *pXsiType*, OSINT16 *xsiTypeIdx*, const OSXMLItemDescr *typetab*[], size_t *typetabsiz*)

This function find index of XSI (XML Schema Instance) type in descriptor table.

Parameters:

pctxt Pointer to context block structure.

pXsiType A pointer to XSI type name.

xsiTypeIdx A XSI type namespace index.

typetab XSI types descriptor table.

typetabsiz Number of descriptors in table.

Returns:

Completion status of operation:

- positive or zero value is type index,
- negative return value is error.

5.4.1.63 int rtXmlpMarkLastEventActive (OSCTXT * *pctxt*)

This function marks current tag as unprocessed.

This will cause the element to be processed again in the next pull-parser function.

Parameters:

pctxt Pointer to context block structure.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.64 void rtXmlpMarkPos (OSCTXT * *pctxt*)

Save current decode position.

Parameters:

pctxt Pointer to context block structure.

5.4.1.65 int rtXmlpMatchEndTag (OSCTXT * *pctxt*, OSINT32 *level*)

This function parse next end tag that matches with given name.

Parameters:

pctxt Pointer to context block structure.

level Nesting level of parsed start tag. When value equal -1 function parse next end tag with current level.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.66 int rtXmlpMatchStartTag (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemLocalName*, OSINT16 *nsidx*)

This function parses the next start tag that matches with given name.

Parameters:

pctxt Pointer to context block structure.

elemLocalName Name of parsed element.

nsidx Namespace index:

- 0 = attribute is unqualified,
- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.4.1.67 OSBOOL rtXmlpNeedDecodeAttributes (OSCTXT * *pctxt*)

This function checks if attributes were previously decoded.

Parameters:

pctxt Pointer to context block structure.

Returns:

State of attributes:

- TRUE = attributes was not decoded,
- FALSE = attributes had been decoded.

5.4.1.68 void rtXmlpResetMarkedPos (OSCTXT * *pctxt*)

Reset saved decode position.

Parameters:

pctxt Pointer to context block structure.

5.4.1.69 void rtXmlpRewindToMarkedPos (OSCTXT * *pctxt*)

Rewind to saved decode position.

Parameters:

pctxt Pointer to context block structure.

5.4.1.70 int rtXmlpSelectAttribute (OSCTXT * *pctxt*, OSXMLNameFragments * *pAttr*, OSINT16 * *nsidx*, size_t *index*)

This function selects attribute to decode.

Parameters:

pctxt Pointer to context block structure.

pAttr Pointer to structure to receive the various parts of an attribute name.

nsidx Pointer to value to receive namespace index:

- 0 = attribute is unqualified,
- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect.

index Index of selected attribute.

Returns:

Completion status of operation:

- positive or zero return value is attribute index in descriptor table,
- negative return value is error.

5.4.1.71 void rtXmlpSetListMode (OSCTXT * *pctxt*)

Sets list mode.

Attribute value or element content is decoded by tokens.

Parameters:

pctxt Pointer to context block structure.

5.4.1.72 OSBOOL rtXmlpSetMixedContentMode (OSCTXT * *pctxt*, OSBOOL *mixedContentMode*)

Sets mixed content mode.

Parameters:

pctxt Pointer to context block structure.

mixedContentMode Enable/disable mixed mode.

Returns:

Previously state of mixed mode.

5.4.1.73 void rtXmlpSetNamespaceTable (OSCTXT * *pctxt*, const OSUTF8CHAR * *namespaceTable*[], size_t *nmNamespaces*)

Sets user namespace table.

Parameters:

pctxt Pointer to context block structure.

namespaceTable Array of namespace URI strings.

nmNamespaces Number of namespaces in table.

5.4.1.74 void rtXmlpSetWhiteSpaceMode (OSCTXT * *pctxt*, OSXMLWhiteSpaceMode *whiteSpaceMode*)

Sets the whitespace treatment mode.

This mode affects the content and attribute values reading. For example, if OSXMLWSM_COLLAPSE mode is set then all spaces in returned data will be already collapsed.

Parameters:

pctxt Pointer to context block structure.

whiteSpaceMode White space mode.

Returns:

Previously set whitespace mode.

5.5 XML run-time error status codes.

This is a list of status codes that can be returned by XML run-time functions and generated code.

Defines

- #define `XML_OK_EOB` 0x7fffffff
End of block marker.
- #define `XML_OK_FRAG` `XML_OK_EOB`
Maintained for backward compatibility.
- #define `XML_E_BASE` -200
Error base.
- #define `XML_E_GENERR` (`XML_E_BASE`)
General error.
- #define `XML_E_INVSYMBOL` (`XML_E_BASE-1`)
An invalid XML symbol (character) was detected at the given point in the parse stream.
- #define `XML_E_TAGMISMATCH` (`XML_E_BASE-2`)
Start/end tag mismatch.
- #define `XML_E_DUPLATTR` (`XML_E_BASE-3`)
Duplicate attribute found.
- #define `XML_E_BADCHARREF` (`XML_E_BASE-4`)
Bad character reference found.
- #define `XML_E_INVMODE` (`XML_E_BASE-5`)
Invalid mode.
- #define `XML_E_UNEXPEOF` (`XML_E_BASE-6`)
Unexpected end of file (document).
- #define `XML_E_NOMATCH` (`XML_E_BASE-7`)
Current tag is not matched to specified one.
- #define `XML_E_ELEMMISRQ` (`XML_E_BASE-8`)
Missing required element.
- #define `XML_E_ELEMSISRQ` (`XML_E_BASE-9`)
Missing required elements.
- #define `XML_E_TOOFWELEMS` (`XML_E_BASE-10`)
The number of elements in a repeating collection was less than the number of elements specified in the XSD minOccurs facet for this type or element.
- #define `XML_E_UNEXPSTARTTAG` (`XML_E_BASE-11`)

Unexpected start tag.

- #define `XML_E_UNEXPENDTAG` (XML_E_BASE-12)
Unexpected end tag.
- #define `XML_E_IDNOTFOU` (XML_E_BASE-13)
Expected identifier not found.
- #define `XML_E_INVTYPEINFO` (XML_E_BASE-14)
Unknown xsi:type.
- #define `XML_E_NSURINOTFOU` (XML_E_BASE-15)
Namespace URI not defined for given prefix.
- #define `XML_E_KEYNOTFOU` (XML_E_BASE-16)
Keyref constraint has some key that not present in refered constraint.
- #define `XML_E_DUPLKEY` (XML_E_BASE-17)
Key or unique constraint has duplicated key.
- #define `XML_E_FLDABSENT` (XML_E_BASE-18)
Some key has no full set of fields.
- #define `XML_E_DUPLFLD` (XML_E_BASE-19)
Some key has more than one value for field.

5.5.1 Detailed Description

This is a list of status codes that can be returned by XML run-time functions and generated code.

In many cases, additional information and parameters for the different errors are stored in the context structure at the time the error is raised. This additional information can be output using the `rtxErrPrint` or `rtxErrLogUsingCB` run-time functions.

5.5.2 Define Documentation

5.5.2.1 #define XML_E_BASE -200

Error base.

XML specific errors start at this base number to distinguish them from common and other error types.

Definition at line 55 of file `rtXmlErrCodes.h`.

5.5.2.2 #define XML_E_ELEMMISRQ (XML_E_BASE-8)

Missing required element.

This status code is returned by the decoder when the decoder knows exactly which element is absent.

Definition at line 116 of file `rtXmlErrCodes.h`.

5.5.2.3 #define XML_E_ELEMSISRQ (XML_E_BASE-9)

Missing required elements.

This status code is returned by the decoder when the number of elements decoded for a given content model group is less than the required number of elements as specified in the schema.

Definition at line 123 of file rtXmlErrCodes.h.

5.5.2.4 #define XML_E_FLDABSENT (XML_E_BASE-18)

Some key has no full set of fields.

It is not valid for key constraint.

Definition at line 194 of file rtXmlErrCodes.h.

5.5.2.5 #define XML_E_NOMATCH (XML_E_BASE-7)

Current tag is not matched to specified one.

Informational code.

Definition at line 110 of file rtXmlErrCodes.h.

5.5.2.6 #define XML_E_NSURINOTFOU (XML_E_BASE-15)

Namespace URI not defined for given prefix.

A namespace URI was not defined using an xmlns attribute for the given prefix.

Definition at line 161 of file rtXmlErrCodes.h.

5.5.2.7 #define XML_E_TAGMISMATCH (XML_E_BASE-2)

Start/end tag mismatch.

The parsed end tag does not match the start tag that was parsed earlier at this level. Indicates document is not well-formed.

Definition at line 85 of file rtXmlErrCodes.h.

5.5.2.8 #define XML_OK_EOB 0x7fffffff

End of block marker.

Definition at line 46 of file rtXmlErrCodes.h.

5.5.2.9 #define XML_OK_FRAG XML_OK_EOB

Maintained for backward compatibility.

Definition at line 49 of file rtXmlErrCodes.h.

5.6 DOM API functions.

Typedefs

- typedef int [OSRTDOMError](#)
0 - OK <0 - Error code (see rtxsrc/rtxErrCodes.h) >0 - Supplementary code

Functions

- EXTERNDOM void [domParserInit](#) ()
Init parser.
- EXTERNDOM void [domParserShutdown](#) ()
Shutdowns parser.
- EXTERNDOM [OSRTDOMError](#) [domParseFile](#) (const char *fileSpec, OSRTDOMDocPtr *pXmlDoc)
Parse the file into a DOM document.
- EXTERNDOM [OSRTDOMError](#) [domGetRootElement](#) (OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr *pNode)
Returns root node for the document.
- EXTERNDOM [OSRTDOMError](#) [domGetDoc](#) (OSRTDOMNodePtr node, OSRTDOMDocPtr *pXmlDoc)
Returns the document for the given element.
- EXTERNDOM void [domFreeDoc](#) (OSRTDOMDocPtr xmlDoc)
Frees document.
- EXTERNDOM [OSRTDOMError](#) [domGetNext](#) (const OSRTDOMNodePtr curNode, OSRTDOMNodePtr *pNextNode)
Returns next element node (down sibling).
- EXTERNDOM [OSRTDOMError](#) [domGetChild](#) (const OSRTDOMNodePtr curNode, OSRTDOMNodePtr *pChildNode)
Returns first (top) child node.
- EXTERNDOM [OSRTDOMError](#) [domGetElementName](#) (const OSRTDOMNodePtr curNode, const OS-UTF8CHAR **ppName, const OSUTF8CHAR **ppNsPrefix, const OSUTF8CHAR **ppNsUri)
Returns node's name and prefix (if any).
- EXTERNDOM int [domGetNodeContent](#) (OSRTDOMContCtxtPtr *ppCtxt, const OSRTDOMNodePtr curNode, const OSUTF8CHAR **ppValue, size_t *pValueLen, OSBOOL *pCdataProcessed)
Gets the node's content.
- EXTERNDOM [OSRTDOMError](#) [domGetNodeFirstAttribute](#) (OSRTDOMAttrCtxtPtr *ppCtxt, const OSRTDOMNodePtr curNode, OSRTDOMAttrPtr *pTopAttrNode)
Returns the pointer to the first (top) attribute of the node.
- EXTERNDOM int [domGetNodeAttributesNum](#) (const OSRTDOMNodePtr curNode)

Returns number of attributes in the node.

- EXTERNDOM [OSRTError domGetNextAttr](#) (OSRTDOMAttrCtxtPtr *ppCtxt, const OSRTDOMAttrPtr curAttrNode, OSRTDOMAttrPtr *pAttrNode)

Returns the next attribute.

- EXTERNDOM [OSRTError domGetAttrData](#) (const OSRTDOMAttrPtr curAttrNode, const OSUTF8CHAR **ppAttrName, const OSUTF8CHAR **ppAttrValue, const OSUTF8CHAR **ppAttrPrefix, const OSUTF8CHAR **ppAttrUri)

Returns the attribute's name and value.

- EXTERNDOM [OSRTError domSaveDoc](#) (OSRTDOMDocPtr xmlDoc, const char *filename)

Saves DOM document to a file.

- EXTERNDOM [OSRTError domCreateDocument](#) (OSCTXT *pctxt, OSRTDOMDocPtr *pXmlDoc, const OSUTF8CHAR *pNodeName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Creates a new document and a root element.

- EXTERNDOM [OSRTError domCreateChild](#) (OSCTXT *pctxt, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *pNodeName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSRTDOMNodePtr *pNewNode)

Creates new child node.

- EXTERNDOM [OSRTError domAddAttribute](#) (OSCTXT *pctxt, OSRTDOMNodePtr node, const OSUTF8CHAR *pAttrName, const OSUTF8CHAR *pAttrValue, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Creates new attribute and adds it to the node.

- EXTERNDOM [OSRTError domAddContent](#) (OSRTDOMNodePtr node, const OSUTF8CHAR *pContent, size_t contentLen)

Adds content (text) to the node.

- EXTERNDOM [OSRTError domAddCdata](#) (OSRTDOMNodePtr node, const OSUTF8CHAR *pContent, size_t contentLen)

Adds CDATA section to the node.

5.6.1 Function Documentation

5.6.1.1 EXTERNDOM OSRTError domAddAttribute (OSCTXT *pctxt, OSRTDOMNodePtr node, const OSUTF8CHAR *pAttrName, const OSUTF8CHAR *pAttrValue, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Creates new attribute and adds it to the node.

Parameters:

pctxt Pointer to context block structure.

node Pointer to the node where attribute to be added.

pAttrName Pointer to the null-terminated string containing name of the attribute.

pAttrValue Pointer to the null-terminated string containing name of the value.

pNS XML namespace information (prefix and URI).
pNSAttrs List of namespace attributes to be added to element.

Returns:

0 - success, otherwise error code.

5.6.1.2 EXTERNDOM OSRTDOMError domAddCdata (OSRTDOMNodePtr *node*, const OSUTF8CHAR **pContent*, size_t *contentLen*)

Adds CDATA section to the node.

Parameters:

node Pointer to the node where content to be added.
pContent Pointer to UTF-8 encoded content to be wrapped by CDATA section.
contentLen Length of the content

Returns:

0 - success, otherwise error code.

5.6.1.3 EXTERNDOM OSRTDOMError domAddContent (OSRTDOMNodePtr *node*, const OSUTF8CHAR **pContent*, size_t *contentLen*)

Adds content (text) to the node.

Parameters:

node Pointer to the node where content to be added.
pContent Pointer to UTF-8 encoded content.
contentLen Length of the content

Returns:

0 - success, otherwise error code.

5.6.1.4 EXTERNDOM OSRTDOMError domCreateChild (OSCTXT **pctxt*, OSRTDOMNodePtr *parentNode*, const OSUTF8CHAR **pNodeName*, OSXMLNamespace **pNS*, OSRTDList **pNSAttrs*, OSRTDOMNodePtr **pNewNode*)

Creates new child node.

Parameters:

pctxt Pointer to context block structure.
parentNode Pointer to the parent node
pNodeName Name of the node
pNS XML namespace information (prefix and URI).
pNSAttrs List of namespace attributes to be added to element.

pNewNode Pointer to pointer to newly created node.

Returns:

0 - success, otherwise error code.

5.6.1.5 EXTERNDOM OSRTDOMError domCreateDocument (OSCTXT * *pctxt*, OSRTDOMDocPtr * *pXmlDoc*, const OSUTF8CHAR * *pNodeName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Creates a new document and a root element.

Parameters:

pctxt Pointer to context block structure.

pXmlDoc Pointer to pointer to the newly created empty DOM document.

pNodeName Name of the node

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns:

0 - success, otherwise error code.

5.6.1.6 EXTERNDOM void domFreeDoc (OSRTDOMDocPtr *xmlDoc*)

Frees document.

Parameters:

xmlDoc Pointer to the DOM document context

5.6.1.7 EXTERNDOM OSRTDOMError domGetAttrData (const OSRTDOMAttrPtr *curAttrNode*, const OSUTF8CHAR ** *ppAttrName*, const OSUTF8CHAR ** *ppAttrValue*, const OSUTF8CHAR ** *ppAttrPrefix*, const OSUTF8CHAR ** *ppAttrUri*)

Returns the attribute's name and value.

Parameters:

curAttrNode Pointer to current attribute node,

ppAttrName Pointer to pointer to receive attribute's name.

ppAttrValue Pointer to pointer to receive attribute's value.

ppAttrPrefix Pointer to pointer to receive namespace's prefix.

ppAttrUri Pointer to pointer to receive namespace's uri.

Returns:

0 - success, otherwise error code.

5.6.1.8 EXTERNDOM OSRTDOMError domGetChild (const OSRTDOMNodePtr *curNode*, OSRTDOMNodePtr * *pChildNode*)

Returns first (top) child node.

Parameters:

curNode Pointer to current node,
pChildNode Pointer to pointer to receive the child node.

Returns:

0 - success, otherwise error code.

5.6.1.9 EXTERNDOM OSRTDOMError domGetDoc (OSRTDOMNodePtr *node*, OSRTDOMDocPtr * *pXmlDoc*)

Returns the document for the given element.

Parameters:

node Pointer to a node.
pXmlDoc Pointer to a pointer to the DOM document context

Returns:

0 - success, otherwise error code.

5.6.1.10 EXTERNDOM OSRTDOMError domGetElementName (const OSRTDOMNodePtr *curNode*, const OSUTF8CHAR ** *ppName*, const OSUTF8CHAR ** *ppNsPrefix*, const OSUTF8CHAR ** *ppNsUri*)

Returns node's name and prefix (if any).

Parameters:

curNode Pointer to current node,
ppName Pointer to pointer to receive the node's local name.
ppNsPrefix Pointer to pointer to receive the node's prefix. May be NULL, if prefix is not important.
ppNsUri Pointer to pointer to receive the namespace's Uri.

Returns:

0 - success, otherwise error code.

5.6.1.11 EXTERNDOM OSRTDOMError domGetNext (const OSRTDOMNodePtr *curNode*, OSRTDOMNodePtr * *pNextNode*)

Returns next element node (down sibling).

Parameters:

curNode Pointer to current node,
pNextNode Pointer to pointer to receive the next node.

Returns:

0 - success, otherwise error code.

5.6.1.12 EXTERNDOM OSRTDOMError domGetNextAttr (OSRTDOMAttrCtxtPtr * ppCtxt, const OSRTDOMAttrPtr curAttrNode, OSRTDOMAttrPtr * pAttrNode)

Returns the next attribute.

Parameters:

ppCtxt Pointer to an implementation-specific context pointer,
curAttrNode Pointer to current attribute node,
pAttrNode Pointer to pointer to receive the next attribute node.

Returns:

0 - success, otherwise error code.

5.6.1.13 EXTERNDOM int domGetNodeAttributesNum (const OSRTDOMNodePtr curNode)

Returns number of attributes in the node.

Parameters:

curNode Pointer to current node,

Returns:

Number of attributes in the node.

5.6.1.14 EXTERNDOM int domGetNodeContent (OSRTDOMContCtxtPtr * ppCtxt, const OSRTDOMNodePtr curNode, const OSUTF8CHAR ** ppValue, size_t * pValueLen, OSBOOL * pCdataProcessed)

Gets the node's content.

Parameters:

ppCtxt Pointer to an implementation-specific content context pointer;
curNode Pointer to the current node;
ppValue Pointer to pointer to receive value;
pValueLen Pointer to value length; may be NULL.
pCdataProcessed Pointer to boolean value; this value will be set to TRUE if CDATA section was proceeded; otherwise FALSE.

Returns:

0 - if content retrieved successfully <0 - the error code;

5.6.1.15 EXTERNDOM OSRTEOMError domGetNodeFirstAttribute (OSRTEOMAttrCtxtPtr * ppCtxt, const OSRTEOMNodePtr curNode, OSRTEOMAttrPtr * pTopAttrNode)

Returns the pointer to the first (top) attribute of the node.

The context pointer will be passed to subsequent calls to domGetNextAttr.

Parameters:

ppCtxt Pointer to an implementation-specific context pointer,

curNode Pointer to current node,

pTopAttrNode Pointer to pointer to receive the first attribute node. domGetNextAttr/domGetPrevAttr functions may be used to get next/previous attributes.

Returns:

0 - success, otherwise error code.

5.6.1.16 EXTERNDOM OSRTEOMError domGetRootElement (OSRTEOMDocPtr xmlDoc, OSRTEOMNodePtr * pNode)

Returns root node for the document.

Parameters:

xmlDoc Pointer to the DOM document context

pNode Pointer to pointer to receive the root node.

Returns:

0 - success, otherwise error code.

5.6.1.17 EXTERNDOM OSRTEOMError domParseFile (const char * fileSpec, OSRTEOMDocPtr * pXmlDoc)

Parse the file into a DOM document.

Parameters:

fileSpec File name

pXmlDoc Pointer to a pointer to newly created DOM document.

Returns:

0 - success, otherwise error code.

5.6.1.18 EXTERNDOM OSRTEOMError domSaveDoc (OSRTEOMDocPtr xmlDoc, const char * filename)

Saves DOM document to a file.

This function is supplementary and it is not obligatory to implement it.

Parameters:

xmlDoc Pointer to the DOM document context.

filename Pointer to file name.

Returns:

0 - success, otherwise error code.

5.7 DOM runtime encode/decode functions.

Functions

- EXTERNDOM int [rtDomAddAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *attrName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds attribute to the node.
- EXTERNDOM int [rtDomAddNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds child node to the parent's node.
- EXTERNDOM int [rtDomAddNSAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr rootNode, OSRTDList *pNSAttrs)
Adds namespace attributes to the root node.
- EXTERNDOM int [rtDomEncXSIAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSBOOL needXSI)
Adds XSI attributes to the node.
- EXTERNDOM int [rtDomDecodeDoc](#) (OSRTDOMDocPtr domDoc, struct OSSAXHandlerBase *pSaxBase)
This function starts decoding of the DOM document.
- EXTERNDOM int [rtDomEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pvalue)
This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncAny](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSXMLSTRING *pXmlData, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
This function encodes a variable of the XSD any type.
- EXTERNDOM int [rtDomEncAnyAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- EXTERNDOM int [rtDomSetNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr curNode)
Adds content or CDATA section to the node.
- EXTERNDOM int [rtDomAddSubTree](#) (OSCTXT *pctxt, OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *pXmlData, size_t dataLen)
This function adds the subtree to the specified node.

5.7.1 Function Documentation

5.7.1.1 EXTERNDOM int rtDomAddAttr (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, const OSUTF8CHAR * *attrName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Adds attribute to the node.

The value is taken from the context's buffer (`pctxt->buffer.data` with the length `pctxt->buffer.byteIndex`). This function resets `pctxt->buffer.byteIndex` to 0.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

node A pointer to a node where attribute to be added.

attrName A pointer to attribute's name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.2 EXTERNDOM int rtDomAddNode (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *parentNode*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Adds child node to the parent's node.

The content (text) is taken from the context's buffer (`pctxt->buffer.data` with the length `pctxt->buffer.byteIndex`). If `pctxt->buffer.byteIndex` is 0 then empty element is added. This function resets `pctxt->buffer.byteIndex` to 0.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

parentNode A pointer to a parent node.

elemName A pointer to element's name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.3 EXTERNDOM int rtDomAddNSAttrs (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *rootNode*, OSRTDList * *pNSAttrs*)

Adds namespace attributes to the root node.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

rootNode A pointer to a root node.

pNSAttrs A pointer to a list of namespace attrs.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.4 EXTERNDOM int rtDomAddSubTree (OSCTXT * *pctxt*, OSRTDOMDocPtr *xmlDoc*, OSRTDOMNodePtr *node*, const OSUTF8CHAR * *pXmlData*, size_t *dataLen*)

This function adds the subtree to the specified node.

The *pXmlData* contains the fragment of XML data. This fragment is parsed to sub-tree and then inserted as children to the 'node'.

Parameters:

pctxt Pointer to the context structure. This context might be used for memory allocations, if necessary.

xmlDoc Pointer to the document

node Pointer to the node where sub-tree to be inserted.

pXmlData Pointer to UTF-8 string representing fragment of XML data. For example, "<elem>data</elem>".

dataLen Length of XML data.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.5 EXTERNDOM int rtDomDecodeDoc (OSRTDOMDocPtr *domDoc*, struct OSSAXHandlerBase * *pSaxBase*)

This function starts decoding of the DOM document.

Parameters:

domDoc A pointer to a DOM-document.

pSaxBase A pointer to SAX handler's base.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.6 EXTERNDOM int rtDomEncAny (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *parentNode*, const OSXMLSTRING * *pXmlData*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

This function encodes a variable of the XSD any type.

This is considered to be a fully-wrapped element of any type (for example: <myType>myData</myType>)

Parameters:

pctxt Pointer to context block structure.

domDoc A pointer to a DOM-document.

parentNode A pointer to a parent node.

pXmlData Value to be encoded. This is a string containing the fully-encoded XML text to be copied to the output stream.

elemName XML element name. A name must be provided. If NULL pointer is passed, no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.7 EXTERNDOM int rtDomEncAnyAttr (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, OSRTDList * *pAnyAttrList*)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.

Parameters:

pctxt Pointer to context block structure.

domDoc A pointer to a DOM-document.

node A pointer to a node where attributes to be added.

pAnyAttrList List of attributes.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.8 EXTERNDOM int rtDomEncString (OSCTXT * *pctxt*, OSXMLSTRING * *pvalue*)

This function encodes a variable of the XSD string type.

Parameters:

- pctxt* Pointer to context block structure.
- pvalue* XML string value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.9 EXTERNDOM int rtDomEncStringValue (OSCTXT * *pctxt*, const OSUTF8CHAR * *pvalue*)

This function encodes a variable of the XSD string type.

Parameters:

- pctxt* Pointer to context block structure.
- pvalue* Null-terminated XML string value to be encoded.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.10 EXTERNDOM int rtDomEncXSIAttrs (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, OSBOOL *needXSI*)

Adds XSI attributes to the node.

Parameters:

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- domDoc* A pointer to a DOM-document.
- node* A pointer to a node.
- needXSI* Determines whether XSI namespace declaration needed.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

5.7.1.11 EXTERNDOM int rtDomSetNode (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *curNode*)

Adds content or CDATA section to the node.

The content (text) is taken from the context's buffer (*pctxt->buffer.data* with the length *pctxt->buffer.byteIndex*). This function resets *pctxt->buffer.byteIndex* to 0.

Parameters:

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

curNode A pointer to a current node.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

Chapter 6

File Documentation

6.1 osrtdom.h File Reference

DOM low-level C encode/decode functions.

```
#include "rtxsrc/rtxCommon.h"  
#include "rtdomsrc/rtxDomDefs.h"  
#include "rtxmlsrc/osrtxml.h"  
#include "rtdomsrc/domAPI.h"  
#include "rtxmlsrc/rtXmlNamespace.h"
```

Functions

- EXTERNDOM int [rtDomAddAttr](#) (OSCTXT *pctx, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *attrName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds attribute to the node.
- EXTERNDOM int [rtDomAddNode](#) (OSCTXT *pctx, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds child node to the parent's node.
- EXTERNDOM int [rtDomAddNSAttrs](#) (OSCTXT *pctx, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr rootNode, OSRTDList *pNSAttrs)
Adds namespace attributes to the root node.
- EXTERNDOM int [rtDomEncXSIAttrs](#) (OSCTXT *pctx, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSBOOL needXSI)
Adds XSI attributes to the node.
- EXTERNDOM int [rtDomDecodeDoc](#) (OSRTDOMDocPtr domDoc, struct OSSAXHandlerBase *pSaxBase)
This function starts decoding of the DOM document.
- EXTERNDOM int [rtDomEncStringValue](#) (OSCTXT *pctx, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD string type.

- EXTERNDOM int [rtDomEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pvalue)
This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncAny](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSXMLSTRING *pXmlData, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
This function encodes a variable of the XSD any type.
- EXTERNDOM int [rtDomEncAnyAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- EXTERNDOM int [rtDomSetNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr curNode)
Adds content or CDATA section to the node.
- EXTERNDOM int [rtDomAddSubTree](#) (OSCTXT *pctxt, OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *pXmlData, size_t dataLen)
This function adds the subtree to the specified node.

6.1.1 Detailed Description

DOM low-level C encode/decode functions.

Definition in file [osrtdom.h](#).

6.2 osrtxml.h File Reference

XML low-level C encode/decode functions.

```
#include "rtxsrc/rtxCommon.h"
#include "rtxmlsrc/rtSaxDefs.h"
#include "rtxsrc/rtxDList.h"
#include "rtxsrc/rtxMemBuf.h"
#include "rtxmlsrc/rtXmlExternDefs.h"
#include "rtxmlsrc/rtXmlErrCodes.h"
#include "rtxmlsrc/rtXmlNamespace.h"
```

Defines

- #define [rtXmlGetEncBufPtr](#)(pctx) (pctx) → buffer.data
This macro returns the start address of the encoded XML message.
- #define [rtXmlGetEncBufLen](#)(pctx) (pctx) → buffer.byteIndex
This macro returns the length of the encoded XML message.

Enumerations

- enum [OSXMLWhiteSpaceMode](#)
Whitespace treatment options.

Functions

- int [rtXmlInitContext](#) (OSCTXT *pctx)
This function initializes a context variable for XML encoding or decoding.
- int [rtXmlInitCtxtAppInfo](#) (OSCTXT *pctx)
This function initializes the XML application info section of the given context.
- int [rtXmlCreateFileInputSource](#) (OSCTXT *pctx, const char *filepath)
This function creates an XML document file input source.
- void [rtXmlMemFreeAnyAttrs](#) (OSCTXT *pctx, OSRTDList *pAnyAttrList)
This function frees a list of anyAttribute that is a member of OSXSAnyType structure.
- int [rtXmlDecBase64Binary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, int length)
This function decodes the contents of a Base64-encoded binary data type into a memory buffer.
- int [rtXmlDecBase64Str](#) (OSCTXT *pctx, OSOCTET *pvalue, OSUINT32 *pnocets, OSINT32 bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.

- int [rtXmlDecBase64StrValue](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, size_t bufSize, size_t srcDataLen)
This function decodes a contents of a Base64-encode binary string into the specified octet array.
- int [rtXmlDecBigInt](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppvalue)
This function will decode a variable of the XSD integer type.
- int [rtXmlDecBool](#) (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int [rtXmlDecDate](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int [rtXmlDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.
- int [rtXmlDecDateTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int [rtXmlDecDecimal](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a decimal data type.
- int [rtXmlDecDouble](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int [rtXmlDecDynBase64Str](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int [rtXmlDecDynHexStr](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int [rtXmlDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *outdata, size_t max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecHexBinary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, int length)
This function decodes the contents of a hex-encoded binary data type into a memory buffer.
- int [rtXmlDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'gMonth' type.

- int [rtXmlDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'gMonthDay' type.

- int [rtXmlDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'gDay' type.

- int [rtXmlDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)

This function decodes the contents of a 32-bit integer data type.

- int [rtXmlDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)

This function decodes the contents of an 8-bit integer data type (i.e.

- int [rtXmlDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)

This function decodes the contents of a 16-bit integer data type.

- int [rtXmlDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)

This function decodes the contents of a 64-bit integer data type.

- int [rtXmlDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)

This function decodes the contents of an unsigned 32-bit integer data type.

- int [rtXmlDecUInt8](#) (OSCTXT *pctxt, OSUINT8 *pvalue)

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

- int [rtXmlDecUInt16](#) (OSCTXT *pctxt, OSUINT16 *pvalue)

This function decodes the contents of an unsigned 16-bit integer data type.

- int [rtXmlDecUInt64](#) (OSCTXT *pctxt, OSUINT64 *pvalue)

This function decodes the contents of an unsigned 64-bit integer data type.

- int [rtXmlDecNSAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue, OSRTDList *pNSAttrs, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)

This function decodes an XML namespace attribute (xmlns).

- const OSUTF8CHAR * [rtXmlDecQName](#) (OSCTXT *pctxt, const OSUTF8CHAR *qname, const OSUTF8CHAR **prefix)

This function decodes an XML qualified name string (QName) type.

- int [rtXmlDecXSIAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue)

This function decodes XML schema instance (XSI) attribute.

- int [rtXmlDecXSIAttrs](#) (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, const char *typeName)

This function decodes XML schema instance (XSI) attributes.

- int [rtXmlDecXmlStr](#) (OSCTXT *pctxt, OSXMLSTRING *outdata)

This function decodes the contents of an XML string data type.

- int [rtXmlParseElementName](#) (OSCTXT *pctxt, OSUTF8CHAR **ppName)

This function parses the initial tag from an XML message.

- int [rtXmlParseElemQName](#) (OSCTXT *pctxt, OSXMLQName *pQName)
This function parses the initial tag from an XML message.
- int [rtXmlEncAny](#) (OSCTXT *pctxt, OSXMLSTRING *pvalue, const OSUTF8CHAR *elemName, OSXML-
Namespace *pNS)
This function encodes a variable of the XSD any type.
- int [rtXmlEncAnyTypeValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD anyType type.
- int [rtXmlEncAnyAttr](#) (OSCTXT *pctxt, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- int [rtXmlEncBase64Binary](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OS-
UTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD base64Binary type.
- int [rtXmlEncBase64BinaryAttr](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OS-
UTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD base64Binary type as an attribute.
- int [rtXmlEncBase64StrValue](#) (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value)
This function encodes a variable of the XSD base64Binary type.
- int [rtXmlEncBigInt](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OS-
XMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncBigIntAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *attrName,
size_t attrNameLen)
This function encodes an XSD integer attribute value.
- int [rtXmlEncBigIntValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes an XSD integer attribute value.
- int [rtXmlEncBitString](#) (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *value, const OSUTF8CHAR
*elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 BIT STRING type.
- int [rtXmlEncBinStrValue](#) (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *data)
This function encodes a binary string value as a sequence of '1's and '0's.
- int [rtXmlEncBool](#) (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *elemName, OSXMLNamespace
*pNS)
This function encodes a variable of the XSD boolean type.
- int [rtXmlEncBoolValue](#) (OSCTXT *pctxt, OSBOOL value)
This function encodes a variable of the XSD boolean type.

- int [rtXmlEncBoolAttr](#) (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes an XSD boolean attribute value.
- int [rtXmlEncDate](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'date' type as a string.
- int [rtXmlEncDateValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a variable of the XSD 'date' type as a string.
- int [rtXmlEncTime](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'time' type as a string.
- int [rtXmlEncTimeValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a variable of the XSD 'time' type as a string.
- int [rtXmlEncDateTime](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric date/time value into an XML string representation.
- int [rtXmlEncDateTimeValue](#) (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric date/time value into an XML string representation.
- int [rtXmlEncDecimal](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDecimalFmt *pFmtSpec)
This function encodes a variable of the XSD decimal type.
- int [rtXmlEncDecimalAttr](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDecimalFmt *pFmtSpec)
This function encodes a variable of the XSD decimal type as an attribute.
- int [rtXmlEncDecimalValue](#) (OSCTXT *pctxt, OSREAL value, const OSDecimalFmt *pFmtSpec, char *pDestBuf, size_t destBufSize)
This function encodes a value of the XSD decimal type.
- int [rtXmlEncDouble](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD double type.
- int [rtXmlEncDoubleAttr](#) (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD double type as an attribute.
- int [rtXmlEncDoubleValue](#) (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)
This function encodes a value of the XSD double or float type.
- int [rtXmlEncEmptyElement](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes an empty element tag value (<elemName/>).

- int `rtXmlEncEndDocument` (OSCTXT *pctxt)
This function adds trailer information and a null terminator at the end of the XML document being encoded.
- int `rtXmlEncEndElement` (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes an end element tag value (</elemName>).
- int `rtXmlEncEndSoapEnv` (OSCTXT *pctxt)
This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).
- int `rtXmlEncEndSoapElems` (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)
This function encodes SOAP end element tags.
- int `rtXmlEncFloat` (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD float type.
- int `rtXmlEncFloatAttr` (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, size_t attrNameLen, const OSDoubleFmt *pFmtSpec)
This function encodes a variable of the XSD float type as an attribute.
- int `rtXmlEncGYear` (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gYear element into an XML string representation.
- int `rtXmlEncGYearMonth` (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gYearMonth element into an XML string representation.
- int `rtXmlEncGMonth` (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gMonth element into an XML string representation.
- int `rtXmlEncGMonthDay` (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gMonthDay element into an XML string representation.
- int `rtXmlEncGDay` (OSCTXT *pctxt, const OSXSDDateTime *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric gDay element into an XML string representation.
- int `rtXmlEncGYearValue` (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gYear value into an XML string representation.
- int `rtXmlEncGYearMonthValue` (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gYearMonth value into an XML string representation.
- int `rtXmlEncGMonthValue` (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gMonth value into an XML string representation.

- int `rtXmlEncGMonthDayValue` (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gMonthDay value into an XML string representation.
- int `rtXmlEncGDayValue` (OSCTXT *pctxt, const OSXSDDateTime *pvalue)
This function encodes a numeric gDay value into an XML string representation.
- int `rtXmlEncHexBinary` (OSCTXT *pctxt, OSUINT32 noctx, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD hexBinary type.
- int `rtXmlEncHexBinaryAttr` (OSCTXT *pctxt, OSUINT32 noctx, const OSOCTET *value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD hexBinary type as an attribute.
- int `rtXmlEncHexStrValue` (OSCTXT *pctxt, OSUINT32 noctx, const OSOCTET *data)
This function encodes a variable of the XSD hexBinary type.
- int `rtXmlEncIndent` (OSCTXT *pctxt)
This function adds indentation whitespace to the output stream.
- int `rtXmlEncInt` (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncIntValue` (OSCTXT *pctxt, OSINT32 value)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncIntAttr` (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD integer type as an attribute (name="value").
- int `rtXmlEncIntPattern` (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSUTF8CHAR *pattern)
This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.
- int `rtXmlEncInt64` (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncInt64Value` (OSCTXT *pctxt, OSINT64 value)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncInt64Attr` (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD integer type as an attribute (name="value").
- int `rtXmlEncNamedBits` (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSUINT32 nbits, const OSOCTET *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 BIT STRING type.
- int `rtXmlEncNSAttrs` (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes namespace declaration attributes at the beginning of an XML document.

- int [rtXmlPrintNSAttrs](#) (const char *name, const OSRTDList *data)
This function prints a list of namespace attributes.
- int [rtXmlEncReal10](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 REAL base 10 type.
- int [rtXmlEncSoapArrayTypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value, size_t itemCount)
This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.
- int [rtXmlEncStartDocument](#) (OSCTXT *pctxt)
This function encodes the XML header text at the beginning of an XML document.
- int [rtXmlEncBOM](#) (OSCTXT *pctxt)
This function encodes the Unicode byte order mark header at the start of the document.
- int [rtXmlEncStartElement](#) (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)
This function encodes a start element tag value (<elemName>).
- int [rtXmlEncStartSoapEnv](#) (OSCTXT *pctxt)
This function encodes a SOAP envelope start element tag.
- int [rtXmlEncStartSoapElems](#) (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)
This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag.
- int [rtXmlEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pxmlstr, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD string type.
- int [rtXmlEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes a variable of the XSD string type.
- int [rtXmlEncStringValue2](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, size_t valueLen)
This function encodes a variable of the XSD string type.
- int [rtXmlEncTermStartElement](#) (OSCTXT *pctxt)
This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator.
- int [rtXmlEncUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR *value, OSUINT32 nchars, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a Unicode string value.
- int [rtXmlEncUTF8Attr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value)
This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.

- int `rtXmlEncUTF8Attr2` (OSCTXT *pctx, const OSUTF8CHAR *name, size_t nameLen, const OSUTF8CHAR *value, size_t valueLen)
This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.
- int `rtXmlEncUTF8Str` (OSCTXT *pctx, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a UTF-8 string value.
- int `rtXmlEncUInt` (OSCTXT *pctx, OSUINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD unsigned integer type.
- int `rtXmlEncUIntValue` (OSCTXT *pctx, OSUINT32 value)
This function encodes a variable of the XSD unsigned integer type.
- int `rtXmlEncUIntAttr` (OSCTXT *pctx, OSUINT32 value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").
- int `rtXmlEncUInt64` (OSCTXT *pctx, OSUINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncUInt64Value` (OSCTXT *pctx, OSUINT64 value)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncUInt64Attr` (OSCTXT *pctx, OSUINT64 value, const OSUTF8CHAR *attrName, size_t attrNameLen)
This function encodes a variable of the XSD integer type as an attribute (name="value").
- int `rtXmlEncXSIAttrs` (OSCTXT *pctx, OSBOOL needXSI)
This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.
- int `rtXmlEncXSITypeAttr` (OSCTXT *pctx, const OSUTF8CHAR *value)
This function encodes an XML schema instance (XSI) type attribute value (xsi:type="value").
- int `rtXmlFreeInputSource` (OSCTXT *pctx)
This function closes an input source that was previously created with one of the create input source functions such as 'rtXmlCreateFileInputSource'.
- int `rtXmlSetEncBufPtr` (OSCTXT *pctx, OSOCTET *bufaddr, size_t bufsiz)
This function is used to set the internal buffer within the run-time library encoding context.
- int `rtXmlGetIndent` (OSCTXT *pctx)
This function returns current XML output indent value.
- OSBOOL `rtXmlGetWriteBOM` (OSCTXT *pctx)
This function returns whether the Unicode byte order mark will be encoded.
- int `rtXmlGetIndentChar` (OSCTXT *pctx)
This function returns current XML output indent character value (default is space).

- int [rtXmlPrepareContext](#) (OSCTXT *pctx)

This function prepares the context for another encode by setting the state back to OSXMLINIT and moving the buffer's cursor back to the beginning of the buffer.
- int [rtXmlSetEncC14N](#) (OSCTXT *pctx, OSBOOL value)

This function sets the option to encode in C14N mode.
- int [rtXmlSetEncXSINamespace](#) (OSCTXT *pctx, OSBOOL value)

This function sets a flag in the context that indicates the XSI namespace declaration (xmlns:xsi) should be added to the encoded XML instance.
- int [rtXmlSetEncDocHdr](#) (OSCTXT *pctx, OSBOOL value)

This function sets the option to add the XML document header (i.e.
- int [rtXmlSetEncodingStr](#) (OSCTXT *pctx, const OSUTF8CHAR *encodingStr)

This function sets the XML output encoding to the given value.
- int [rtXmlSetFormatting](#) (OSCTXT *pctx, OSBOOL doFormatting)

This function sets XML output formatting to the given value.
- int [rtXmlSetIndent](#) (OSCTXT *pctx, OSUINT8 indent)

This function sets XML output indent to the given value.
- int [rtXmlSetIndentChar](#) (OSCTXT *pctx, char indentChar)

This function sets XML output indent character to the given value.
- void [rtXmlSetNamespacesSet](#) (OSCTXT *pctx, OSBOOL value)

This function sets the context 'namespaces are set' flag.
- int [rtXmlSetNSPrefixLinks](#) (OSCTXT *pctx, OSRTDList *pNSAttrs)

This function sets namespace prefix/URI links in the namespace prefix stack in the context structure.
- int [rtXmlSetSchemaLocation](#) (OSCTXT *pctx, const OSUTF8CHAR *schemaLocation)

This function sets the XML Schema Instance (xsi) schema location attribute to be added to an encoded document.
- int [rtXmlSetNoNSSchemaLocation](#) (OSCTXT *pctx, const OSUTF8CHAR *schemaLocation)

This function sets the XML Schema Instance (xsi) no namespace schema location attribute to be added to an encoded document.
- void [rtXmlSetSoapVersion](#) (OSCTXT *pctx, OSUINT8 version)

This function sets the SOAP version number.
- int [rtXmlSetXSITypeAttr](#) (OSCTXT *pctx, const OSUTF8CHAR *xsiType)

This function sets the XML Schema Instance (xsi) type attribute value.
- int [rtXmlSetWriteBOM](#) (OSCTXT *pctx, OSBOOL write)

This function sets whether the Unicode byte order mark is encoded.
- int [rtXmlMatchHexStr](#) (OSCTXT *pctx, size_t minLength, size_t maxLength)

This function tests the context buffer for containing a correct hexadecimal string.

- int [rtXmlMatchBase64Str](#) (OSCTXT *pctx, size_t minLength, size_t maxLength)
This function tests the context buffer for containing a correct base64 string.
- int [rtXmlMatchDate](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct date string.
- int [rtXmlMatchTime](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct time string.
- int [rtXmlMatchDateTime](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct dateTime string.
- int [rtXmlMatchGYear](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct gYear string.
- int [rtXmlMatchGYearMonth](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct gYearMonth string.
- int [rtXmlMatchGMonth](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct gMonth string.
- int [rtXmlMatchGMonthDay](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct gMonthDay string.
- int [rtXmlMatchGDay](#) (OSCTXT *pctx)
This function tests the context buffer for containing a correct gDay string.
- OSUTF8CHAR * [rtXmlNewQName](#) (OSCTXT *pctx, const OSUTF8CHAR *localName, const OSUTF8CHAR *prefix)
This function creates a new QName given the localName and prefix parts.
- OSBOOL [rtXmlCmpBase64Str](#) (OSUINT32 noctx, const OSOCTET *data1, const OSUTF8CHAR *data2)
This function compares an array of octets to a base64 string.
- OSBOOL [rtXmlCmpHexStr](#) (OSUINT32 noctx, const OSOCTET *data1, const OSUTF8CHAR *data2)
This function compares an array of octets to a hex string.
- const OSUTF8CHAR * [rtSaxGetAttrValue](#) (const OSUTF8CHAR *attrName, const OSUTF8CHAR *const *attrs)
This function looks up an attribute in the attribute array returned by SAX to the startElement function.
- OSINT16 [rtSaxGetElemID](#) (OSINT16 *pState, OSINT16 prevElemIdx, const OSUTF8CHAR *localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT16 *fstab, OSINT16 fstabRows, OSINT16 fstabCols)
This function looks up a sequence element name in the given element info array.
- OSINT16 [rtSaxGetElemID8](#) (OSINT16 *pState, OSINT16 prevElemIdx, const OSUTF8CHAR *localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT8 *fstab, OSINT16 fstabRows, OSINT16 fstabCols)

This function is a space optimized version of `rtSaxGetElemID`.

- OSBOOL `rtSaxHasXMLNSAttrs` (const OSUTF8CHAR *const *attrs)
This function checks if the given attribute list contains one or more XML namespace attributes (xmlns).
- OSBOOL `rtSaxIsEmptyBuffer` (OSCTXT *pctxt)
This function checks if the buffer in the context is empty or not.
- int `rtSaxStrListParse` (OSCTXT *pctxt, OSRTMEMBUF *pMemBuf, OSRTDList *pvalue)
This function parses the list of strings.
- int `rtSaxSortAttrs` (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, OSUINT16 **order)
This function sorts a SAX attribute list in ascending order based on attribute name.
- int `rtSaxStrListMatch` (OSCTXT *pctxt)
This function matches the list of strings.
- int `rtXmlWriteToFile` (OSCTXT *pctxt, const char *filename)
This function writes the encoded XML message stored in the context message buffer out to a file.
- int `rtXmlpDecAny` (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int `rtXmlpDecAnyAttrStr` (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrStr, size_t index)
This function decodes an any attribute string.
- int `rtXmlpDecAnyElem` (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int `rtXmlpDecBase64Str` (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocets, OSINT32 bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int `rtXmlpDecBigInt` (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function will decode a variable of the XSD integer type.
- int `rtXmlpDecBitString` (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes a bit string value.
- int `rtXmlpDecBool` (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int `rtXmlpDecDate` (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int `rtXmlpDecDateTime` (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int `rtXmlpDecDecimal` (OSCTXT *pctxt, OSREAL *pvalue, int totalDigits, int fractionDigits)
This function decodes the contents of a decimal data type.

- int [rtXmlpDecDouble](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int [rtXmlpDecDynBase64Str](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int [rtXmlpDecDynBitString](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a bit string value.
- int [rtXmlpDecDynHexStr](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int [rtXmlpDecDynUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR **ppdata, OSUINT32 *pnchars)
This function decodes a Unicode string data type.
- int [rtXmlpDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlpDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *out, size_t max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlpDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlpDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlpDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlpDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlpDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlpDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlpDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlpDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlpDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlpDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.

- int [rtXmlpDecNamedBits](#) (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes the contents of a named bit field.
- int [rtXmlpDecStrList](#) (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int [rtXmlpDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.
- int [rtXmlpDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.
- int [rtXmlpDecUInt8](#) (OSCTXT *pctxt, OSOCTET *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.
- int [rtXmlpDecUInt16](#) (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int [rtXmlpDecUInt64](#) (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.
- int [rtXmlpDecXmlStr](#) (OSCTXT *pctxt, OSXMLSTRING *outdata)
This function decodes the contents of an XML string data type.
- int [rtXmlpDecXmlStrList](#) (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int [rtXmlpDecXSIAttr](#) (OSCTXT *pctxt, const OSXMLNameFragments *attrName)
This function decodes XSI (XML Schema Instance) and XML namespace attributes that may be present in any arbitrary XML element within a document.
- int [rtXmlpDecXSISTypeAttr](#) (OSCTXT *pctxt, const OSXMLNameFragments *attrName, const OS-UTF8CHAR **ppAttrValue)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int [rtXmlpGetAttributeID](#) (const OSXMLStrFragment *attrName, OSINT16 nsidx, size_t nAttr, const OSXMLAttrDescr attrNames[], OSUINT32 attrPresent[])
This function finds an attribute in the descriptor table.
- int [rtXmlpGetNextElem](#) (OSCTXT *pctxt, OSXMLElemDescr *pElem, OSINT32 level)
This function parse the next element start tag.
- int [rtXmlpGetNextElemID](#) (OSCTXT *pctxt, const OSXMLElemIDRec *tab, size_t nrows, OSINT32 level, OSBOOL continueParse)
This function parses the next start tag and finds the index of the element name in the descriptor table.
- int [rtXmlpMarkLastEventActive](#) (OSCTXT *pctxt)
This function marks current tag as unprocessed.

- int [rtXmlpMatchStartTag](#) (OSCTXT *pctx, const OSUTF8CHAR *elemLocalName, OSINT16 nsidx)
This function parses the next start tag that matches with given name.
- int [rtXmlpMatchEndTag](#) (OSCTXT *pctx, OSINT32 level)
This function parse next end tag that matches with given name.
- OSBOOL [rtXmlpHasAttributes](#) (OSCTXT *pctx)
This function checks accessibility of attributes.
- int [rtXmlpGetAttributeCount](#) (OSCTXT *pctx)
This function returns number of attributes in last processed start tag.
- int [rtXmlpSelectAttribute](#) (OSCTXT *pctx, OSXMLNameFragments *pAttr, OSINT16 *nsidx, size_t index)
This function selects attribute to decode.
- OSINT32 [rtXmlpGetCurrentLevel](#) (OSCTXT *pctx)
This function returns current nesting level.
- void [rtXmlpSetWhiteSpaceMode](#) (OSCTXT *pctx, OSXMLWhiteSpaceMode whiteSpaceMode)
Sets the whitespace treatment mode.
- OSBOOL [rtXmlpSetMixedContentMode](#) (OSCTXT *pctx, OSBOOL mixedContentMode)
Sets mixed content mode.
- void [rtXmlpSetListMode](#) (OSCTXT *pctx)
Sets list mode.
- OSBOOL [rtXmlpListHasItem](#) (OSCTXT *pctx)
Check for end of decoded token list.
- void [rtXmlpCountListItems](#) (OSCTXT *pctx, OSUINT32 *itemCnt)
Count tokens in list.
- int [rtXmlpGetNextSeqElemID](#) (OSCTXT *pctx, const OSXMLElemIDRec *tab, const OSXMLGroupDesc *pGroup, int curID, int lastMandatoryID, OSBOOL groupMode)
This function parses the next start tag and find index of element name in descriptor table.
- int [rtXmlpGetNextAllElemID](#) (OSCTXT *pctx, const OSXMLElemIDRec *tab, size_t nrows, const OSUINT8 *pOrder, OSUINT32 nOrder, OSUINT32 maxOrder, int anyID)
This function parses the next start tag and finds index of element name in descriptor table.
- int [rtXmlpGetNextAllElemID16](#) (OSCTXT *pctx, const OSXMLElemIDRec *tab, size_t nrows, const OSUINT16 *pOrder, OSUINT32 nOrder, OSUINT32 maxOrder, int anyID)
This function parses the next start tag and finds index of element name in descriptor table.
- void [rtXmlpSetNamespaceTable](#) (OSCTXT *pctx, const OSUTF8CHAR *namespaceTable[], size_t nmNamespaces)
Sets user namespace table.
- int [rtXmlpCreateReader](#) (OSCTXT *pctx)

Creates pull parser reader structure within the context.

- void **rtXmlpHideAttributes** (OSCTXT *pctxt)
Disable access to attributes.
- OSBOOL **rtXmlpNeedDecodeAttributes** (OSCTXT *pctxt)
This function checks if attributes were previously decoded.
- void **rtXmlpMarkPos** (OSCTXT *pctxt)
Save current decode position.
- void **rtXmlpRewindToMarkedPos** (OSCTXT *pctxt)
Rewind to saved decode position.
- void **rtXmlpResetMarkedPos** (OSCTXT *pctxt)
Reset saved decode position.
- int **rtXmlpGetXSITypeAttr** (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrValue, OSINT16 *nsidx, size_t *pLocalOffs)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int **rtXmlpGetXmlnsAttrs** (OSCTXT *pctxt, OSRTDList *pNSAttrs)
This function decodes namespace attributes from start tag and adds them to the given list.
- int **rtXmlpDecXSIAttrs** (OSCTXT *pctxt)
This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.
- OSBOOL **rtXmlpIsEmptyElement** (OSCTXT *pctxt)
Check element content: empty or not.
- int **rtXmlEncAttrC14N** (OSCTXT *pctxt)
This function used only in C14 mode.
- OSBOOL **rtXmlpIsLastEventDone** (OSCTXT *pctxt)
Check processing status of current tag.
- int **rtXmlpGetXSITypeIndex** (OSCTXT *pctxt, const OSXMLItemDescr typetab[], size_t typetabsiz)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.
- int **rtXmlpLookupXSITypeIndex** (OSCTXT *pctxt, const OSUTF8CHAR *pXsiType, OSINT16 xsiTypeIdx, const OSXMLItemDescr typetab[], size_t typetabsiz)
This function find index of XSI (XML Schema Instance) type in descriptor table.
- void **rtXmlpForceDecodeAsGroup** (OSCTXT *pctxt)
Disable skipping of unknown elements in optional sequence tail.
- OSBOOL **rtXmlpIsDecodeAsGroup** (OSCTXT *pctxt)
This function checks if "decode as group" mode was forced.
- OSBOOL **rtXmlpIsUTF8Encoding** (OSCTXT *pctxt)
This function checks if the encoding specified in XML header is UTF-8.

6.2.1 Detailed Description

XML low-level C encode/decode functions.

Definition in file [osrxml.h](#).

6.2.2 Function Documentation

6.2.2.1 `const OSUTF8CHAR* rtSaxGetAttrValue (const OSUTF8CHAR * attrName, const OSUTF8CHAR *const * attrs)`

This function looks up an attribute in the attribute array returned by SAX to the startElement function.

Parameters:

attrName Name of the attribute to find.

attrs Attribute array returned in SAX startElement function. This is an array of character strings containing name1, value1, name2, value2, ... List is terminated by a null name.

Returns:

Pointer to character string containing attribute value or NULL if attrName not found.

6.2.2.2 `OSINT16 rtSaxGetElemID (OSINT16 * pState, OSINT16 prevElemIdx, const OSUTF8CHAR * localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT16 * fstab, OSINT16 fstabRows, OSINT16 fstabCols)`

This function looks up a sequence element name in the given element info array.

If ensures elements are received in the correct order and also sets the required element count variable.

Parameters:

pState The pointer to state variable to be changed.

prevElemIdx Previous index of element. The search will be started from this element for better performance.

localName Local name of XML element

nsidx Namespace index

idtab Element ID table

fstab Finite state table

fstabRows Number of rows in *fstab*.

fstabCols Number of columns in *fstab*.

6.2.2.3 `OSINT16 rtSaxGetElemID8 (OSINT16 * pState, OSINT16 prevElemIdx, const OSUTF8CHAR * localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT8 * fstab, OSINT16 fstabRows, OSINT16 fstabCols)`

This function is a space optimized version of `rtSaxGetElemID`.

It operates with array of 8-bit integers (OSINT8) instead of 32-bit integers (int).

Parameters:

pState The pointer to state variable to be changed.

prevElemIdx Previous index of element. The search will be started from this element + 1 for better performance.

localName Local name of XML element

nsidx Namespace index

idtab Element ID table

fstab Finite state table (array of 8-bit integers)

fstabRows Number of rows in *fstab*.

fstabCols Number of columns in *fstab*.

6.2.2.4 OSBOOL rtSaxHasXMLNSAttrs (const OSUTF8CHAR *const * attrs)

This function checks if the given attribute list contains one or more XML namespace attributes (xmlns).

Parameters:

attrs Attribute list in form passed by parser into SAX startElement function.

Returns:

TRUE, if xmlns attribute found in list.

6.2.2.5 OSBOOL rtSaxIsEmptyBuffer (OSCTXT * pctx)

This function checks if the buffer in the context is empty or not.

Parameters:

pctx Pointer to OSCTXT structure

Returns:

TRUE, if the buffer contains empty string.

6.2.2.6 int rtSaxSortAttrs (OSCTXT * pctx, const OSUTF8CHAR *const * attrs, OSUINT16 ** order)

This function sorts a SAX attribute list in ascending order based on attribute name.

It currently only supports unqualified attributes.

Parameters:

pctx Pointer to OSCTXT structure.

attrs Standard SAX attribute list. Entry *i* is attribute name and *i+1* is value. List is terminated by a null name.

order Order array containing the order of sorted attributes. This array is allocated using *rtxMemAlloc*, it can be freed using *rtxMemFreePtr* or will be freed when the context is freed. The list holds indices to name items in the attribute list that is passed in.

Returns:

If success, positive value contains number of attributes in *attrs*; if failure, negative status code.

6.2.2.7 int rtSaxStrListMatch (OSCTXT * *pctxt*)

This function matches the list of strings.

It is used for matching NMTOKENS, IDREFS, NMENTITIES.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

0 - if success, negative value is error.

6.2.2.8 int rtSaxStrListParse (OSCTXT * *pctxt*, OSRTMEMBUF * *pMemBuf*, OSRTDList * *pvalue*)

This function parses the list of strings.

It is used for parsing NMTOKENS, IDREFS, NMENTITIES.

Parameters:

pctxt Pointer to OSCTXT structure. Can be NULL, if *pMemBuf* is not NULL.

pMemBuf Pointer to memory buffer structure. Can be NULL, if *pctxt* is not NULL.

pvalue Doubly-linked list for parsed strings.

Returns:

0 - if success, negative value is error.

6.2.2.9 OSBOOL rtXmlCmpBase64Str (OSUINT32 *nocts1*, const OSOCTET * *data1*, const OSUTF8CHAR * *data2*)

This function compares an array of octets to a base64 string.

Parameters:

nocts1 Number of octets in *data1*.

data1 Pointer to array of OSOCTET.

data2 Pointer to null-terminated array of OSUTF8CHAR.

Returns:

TRUE if *data2* is a base64 string representation of *data1*, false otherwise.

6.2.2.10 OSBOOL rtXmlCmpHexStr (OSUINT32 *nocts1*, const OSOCTET * *data1*, const OSUTF8CHAR * *data2*)

This function compares an array of octets to a hex string.

Parameters:

nocts1 Number of octets in *data1*.

data1 Pointer to array of OSOCTET.

data2 Pointer to null-terminated array of OSUTF8CHAR.

Returns:

TRUE if data2 is a hex string representation of data1, false otherwise.

6.2.2.11 int rtXmlCreateFileInputSource (OSCTXT * *pctxt*, const char * *filepath*)

This function creates an XML document file input source.

The document can then be decoded by invoking an XML decode function.

Parameters:

pctxt Pointer to context block structure.

filepath Full pathname of XML document file to open.

Returns:

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.12 int rtXmlInitContext (OSCTXT * *pctxt*)

This function initializes a context variable for XML encoding or decoding.

Parameters:

pctxt Pointer to OSCTXT structure

6.2.2.13 int rtXmlInitCtxtAppInfo (OSCTXT * *pctxt*)

This function initializes the XML application info section of the given context.

Parameters:

pctxt Pointer to OSCTXT structure

6.2.2.14 int rtXmlMatchBase64Str (OSCTXT * *pctxt*, size_t *minLength*, size_t *maxLength*)

This function tests the context buffer for containing a correct base64 string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

minLength A minimal length of expected string.

maxLength A maximal length of expected string.

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.15 int rtXmlMatchDate (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct date string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.16 int rtXmlMatchDateTime (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct dateTime string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.17 int rtXmlMatchGDay (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gDay string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.18 int rtXmlMatchGMonth (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gMonth string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.19 int rtXmlMatchGMonthDay (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gMonthDay string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.20 int rtXmlMatchGYear (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gYear string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.21 int rtXmlMatchGYearMonth (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gYearMonth string.

It does not decode the value.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.22 `int rtXmlMatchHexStr (OSCTXT * pctxt, size_t minLength, size_t maxLength)`

This function tests the context buffer for containing a correct hexadecimal string.

It does not decode the value.

Parameters:

- pctxt* Pointer to OSCTXT structure
- minLength* A minimal length of expected string.
- maxLength* A maximal length of expected string.

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.23 `int rtXmlMatchTime (OSCTXT * pctxt)`

This function tests the context buffer for containing a correct time string.

It does not decode the value.

Parameters:

- pctxt* Pointer to OSCTXT structure

Returns:

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

6.2.2.24 `void rtXmlMemFreeAnyAttrs (OSCTXT * pctxt, OSRTDList * pAnyAttrList)`

This function frees a list of anyAttribute that is a member of OSXSAnyType structure.

Parameters:

- pctxt* Pointer to context block structure.
- pAnyAttrList* Pointer to list of anyAttribute that is to be freed.

6.2.2.25 `OSUTF8CHAR* rtXmlNewQName (OSCTXT * pctxt, const OSUTF8CHAR * localName, const OSUTF8CHAR * prefix)`

This function creates a new QName given the localName and prefix parts.

Parameters:

- pctxt* Pointer to a context structure.
- localName* Element local name.
- prefix* Namespace prefix.

Returns:

QName value. Memory for the value will have been allocated by `rtxMemAlloc` and thus must be freed using one of the `rtxMemFree` functions. The value will be NULL if no dynamic memory was available.

6.2.2.26 **int rtXmlPrepareContext (OSCTXT * *pctxt*)**

This function prepares the context for another encode by setting the state back to OSXMLINIT and moving the buffer's cursor back to the beginning of the buffer.

Parameters:

pctxt Pointer to OSCTXT structure

Returns:

0 if OK, negative status code if error.

6.2.2.27 **int rtXmlSetEncC14N (OSCTXT * *pctxt*, OSBOOL *value*)**

This function sets the option to encode in C14N mode.

Parameters:

pctxt Pointer to OSCTXT structure

value Boolean value: true = C14N mode enabled.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.28 **int rtXmlSetEncDocHdr (OSCTXT * *pctxt*, OSBOOL *value*)**

This function sets the option to add the XML document header (i.e. <?xml version="1.0" encoding="UTF-8"?>) to the XML output stream.

Parameters:

pctxt Pointer to OSCTXT structure

value Boolean value: true = add document header

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.29 **int rtXmlSetEncodingStr (OSCTXT * *pctxt*, const OSUTF8CHAR * *encodingStr*)**

This function sets the XML output encoding to the given value.

Currently, only UTF-8 encoding is supported.

Parameters:

pctxt Pointer to OSCTXT structure

encodingStr XML output encoding format

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.30 **int rtXmlSetEncXSINamespace (OSCTXT * *pctxt*, OSBOOL *value*)**

This function sets a flag in the context that indicates the XSI namespace declaration (xmlns:xsi) should be added to the encoded XML instance.

Parameters:

pctxt Pointer to OSCTXT structure

value Boolean value: true = encode XSI namespace attribute.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.31 **int rtXmlSetFormatting (OSCTXT * *pctxt*, OSBOOL *doFormatting*)**

This function sets XML output formatting to the given value.

If TRUE (the default), the XML document is formatted with indentation and newlines. If FALSE, all whitespace between elements is suppressed. Turning formatting off can provide more compressed documents and also a more canonical representation which is important for security applications. Also the function 'rtXmlSetIndent' might be used to set the exact size of indentation.

Parameters:

pctxt Pointer to OSCTXT structure

doFormatting Boolean value indicating if formatting is to be done

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.32 **int rtXmlSetIndent (OSCTXT * *pctxt*, OSUINT8 *indent*)**

This function sets XML output indent to the given value.

Parameters:

pctxt Pointer to OSCTXT structure

indent Number of spaces per indent. Default is 3.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.33 **int rtXmlSetIndentChar (OSCTXT * *pctxt*, char *indentChar*)**

This function sets XML output indent character to the given value.

Parameters:

pctxt Pointer to OSCTXT structure

indentChar Indent character. Default is space.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.34 void rtXmlSetNamespacesSet (OSCTXT * *pctxt*, OSBOOL *value*)

This function sets the context 'namespaces are set' flag.

This indicates that namespace declarations have been set either by the decoder or externally by the end user. It is used by the encoder to know not to set the default namespaces specified in the schema before starting encoding.

Parameters:

pctxt Pointer to OSCTXT structure.

value Boolean value to which flag is to be set.

6.2.2.35 int rtXmlSetNoNSSchemaLocation (OSCTXT * *pctxt*, const OSUTF8CHAR * *schemaLocation*)

This function sets the XML Schema Instance (xsi) no namespace schema location attribute to be added to an encoded document.

This attribute is optional: if not set, no xsi:noNamespaceSchemaLocation attribute will be added.

Parameters:

pctxt Pointer to OSCTXT structure

schemaLocation Schema location attribute value

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.36 int rtXmlSetNSPrefixLinks (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function sets namespace prefix/URI links in the namespace prefix stack in the context structure.

Parameters:

pctxt Pointer to OSCTXT structure.

pNSAttrs List of namespace attributes.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.37 int rtXmlSetSchemaLocation (OSCTXT * *pctxt*, const OSUTF8CHAR * *schemaLocation*)

This function sets the XML Schema Instance (xsi) schema location attribute to be added to an encoded document. This attribute is optional: if not set, no xsi:schemaLocation attribute will be added.

Parameters:

pctxt Pointer to OSCTXT structure
schemaLocation Schema location attribute value

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.38 void rtXmlSetSoapVersion (OSCTXT * *pctxt*, OSUINT8 *version*)

This function sets the SOAP version number.

Parameters:

pctxt Pointer to OSCTXT structure
version SOAP version number as 2 digit integer (for example, 11 is SOAP version 1.1, 12 is version 1.2, etc.)

6.2.2.39 int rtXmlSetWriteBOM (OSCTXT * *pctxt*, OSBOOL *write*)

This function sets whether the Unicode byte order mark is encoded.

Parameters:

pctxt Pointer to OSCTXT structure
write TRUE to encode BOM, FALSE to not encode BOM.

Returns:

Status of operation: 0 if OK, negative status code if error.

6.2.2.40 int rtXmlSetXSITypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *xsiType*)

This function sets the XML Schema Instance (xsi) type attribute value. This will cause an xsi:type attribute to be added to the top level element in an encoded XML instance.

Parameters:

pctxt Pointer to OSCTXT structure
xsiType xsi:type attribute value

Returns:

Status of operation: 0 if OK, negative status code if error.

6.3 rtXmlErrCodes.h File Reference

List of numeric status codes that can be returned by ASN1C run-time functions and generated code.

```
#include "rtxsrc/rtxErrCodes.h"
```

Defines

- #define [XML_OK_EOB](#) 0x7fffffff
End of block marker.
- #define [XML_OK_FRAG](#) XML_OK_EOB
Maintained for backward compatibility.
- #define [XML_E_BASE](#) -200
Error base.
- #define [XML_E_GENERR](#) (XML_E_BASE)
General error.
- #define [XML_E_INVSYMBOL](#) (XML_E_BASE-1)
An invalid XML symbol (character) was detected at the given point in the parse stream.
- #define [XML_E_TAGMISMATCH](#) (XML_E_BASE-2)
Start/end tag mismatch.
- #define [XML_E_DUPLATTR](#) (XML_E_BASE-3)
Duplicate attribute found.
- #define [XML_E_BADCHARREF](#) (XML_E_BASE-4)
Bad character reference found.
- #define [XML_E_INVMODE](#) (XML_E_BASE-5)
Invalid mode.
- #define [XML_E_UNEXPEOF](#) (XML_E_BASE-6)
Unexpected end of file (document).
- #define [XML_E_NOMATCH](#) (XML_E_BASE-7)
Current tag is not matched to specified one.
- #define [XML_E_ELEMMISRQ](#) (XML_E_BASE-8)
Missing required element.
- #define [XML_E_ELEMSISRQ](#) (XML_E_BASE-9)
Missing required elements.
- #define [XML_E_TOOFWELEMS](#) (XML_E_BASE-10)
The number of elements in a repeating collection was less than the number of elements specified in the XSD minOccurs facet for this type or element.

- #define [XML_E_UNEXPSTARTTAG](#) (XML_E_BASE-11)
Unexpected start tag.
- #define [XML_E_UNEXPENDTAG](#) (XML_E_BASE-12)
Unexpected end tag.
- #define [XML_E_IDNOTFOU](#) (XML_E_BASE-13)
Expected identifier not found.
- #define [XML_E_INVTYPEINFO](#) (XML_E_BASE-14)
Unknown xsi:type.
- #define [XML_E_NSURINOTFOU](#) (XML_E_BASE-15)
Namespace URI not defined for given prefix.
- #define [XML_E_KEYNOTFOU](#) (XML_E_BASE-16)
Keyref constraint has some key that not present in refered constraint.
- #define [XML_E_DUPLKEY](#) (XML_E_BASE-17)
Key or unique constraint has duplicated key.
- #define [XML_E_FLDABSENT](#) (XML_E_BASE-18)
Some key has no full set of fields.
- #define [XML_E_DUPLFLD](#) (XML_E_BASE-19)
Some key has more than one value for field.

6.3.1 Detailed Description

List of numeric status codes that can be returned by ASN1C run-time functions and generated code.

Definition in file [rtXmlErrCodes.h](#).

6.4 `rtXmlExternDefs.h` File Reference

XML external definitions macro.

6.4.1 Detailed Description

XML external definitions macro.

This is used for Windows to properly declare function scope within DLL's.

Definition in file [rtXmlExternDefs.h](#).

6.5 rtXmlKeyArray.h File Reference

- Implementation of a dynamic pointer sorted array.

```
#include "rtxsrc/rtxContext.h"
```

```
#include "rtxmlsrc/rtXmlExternDefs.h"
```

6.5.1 Detailed Description

- Implementation of a dynamic pointer sorted array.

Definition in file [rtXmlKeyArray.h](#).

6.6 rtXmlNamespace.h File Reference

XML namespace handling structures and function definitions.

```
#include "rtxsrc/rtxContext.h"
#include "rtxsrc/rtxDynPtrArray.h"
#include "rtxsrc/rtxXmlQName.h"
#include "rtxmlsrc/rtXmlExternDefs.h"
```

Defines

- #define [RTXMLNSSETQNAME](#)(qname, pNS)
This macro populates the given QName structure with information from the given namespace structure (namespace URI and prefix).

Functions

- OSXMLNamespace * [rtXmlNSAddNamespace](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri)
This function adds a namespace to the context namespace list.
- OSBOOL [rtXmlNSEqual](#) (OSXMLNamespace *pNS1, OSXMLNamespace *pNS2)
This function checks if two namespace records are equal.
- void [rtXmlNSFreeAttrList](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs)
This function frees dynamic memory used to hold namespace attribute values.
- const OSUTF8CHAR * [rtXmlNSGetPrefix](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri)
This function gets a namespace prefix assigned to the given URI.
- const OSUTF8CHAR * [rtXmlNSGetPrefixUsingIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri, OSUINT32 idx)
This function gets a namespace prefix assigned to the given URI using the given index to select a specific prefix from the URI/prefix map.
- OSUINT32 [rtXmlNSGetPrefixCount](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri)
This function returns the total number of prefixes currently assigned to the given URI.
- int [rtXmlNSGetPrefixIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri, const OSUTF8CHAR *prefix, OSUINT32 *pcount)
This function gets the index of a given prefix in the internal list of prefixes maintained for a given URI in the namespace stack.
- const OSUTF8CHAR * [rtXmlNSGetQName](#) (OSCTXT *pctxt, OSUTF8CHAR *buf, size_t bufsiz, const OSUTF8CHAR *uri, const OSUTF8CHAR *localName)
This function creates a QName in the given fixed-size buffer.
- const OSUTF8CHAR * [rtXmlNSGetAttrQName](#) (OSCTXT *pctxt, OSUTF8CHAR *buf, size_t bufsiz, OSXMLNamespace *pNS, const OSUTF8CHAR *localName, OSRTDList *pNSAttrs)

This function creates a QName for a qualified attribute.

- OSXMLNamespace * [rtXmlNSLookupURI](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri)
This function looks up a namespace in the context namespace stack using URI as the key value.
- OSXMLNamespace * [rtXmlNSLookupURIInList](#) (OSRTDList *pNSAttrs, const OSUTF8CHAR *uri)
This function looks up a namespace in the given list using URI as the key value.
- const OSUTF8CHAR * [rtXmlNSLookupPrefix](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix)
This function looks up a namespace in the context namespace list using the prefix as the key value.
- const OSUTF8CHAR * [rtXmlNSLookupPrefixFrag](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix, size_t prefixLen)
This function looks up a namespace in the context namespace list using the prefix as the key value.
- void [rtXmlNSRemoveAll](#) (OSCTXT *pctxt)
This function removes all namespaces from the context namespace list and frees the dynamic memory used to hold the names.
- OSXMLNamespace * [rtXmlNSSetNamespace](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri, OSBOOL override)
This function sets a namespace in the context namespace list.
- const OSUTF8CHAR * [rtXmlNSNewPrefix](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri, OSRTDList *pNSAttrs)
This function returns the next unused prefix of the form "nsX" where X is a number.
- int [rtXmlNSAddPrefixLink](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)
Add a prefix link at the current stack level.
- int [rtXmlNSFreeAllPrefixLinks](#) (OSCTXT *pctxt, OSXMLNSPfxLinkStackNode *pStackNode)
Free all prefixes links in the given namespace stack entry.
- int [rtXmlNSFreePrefixLink](#) (OSCTXT *pctxt, OSXMLNSPfxLink *plink)
Free all data within a given namespace prefix link structure.
- int [rtXmlNSGetIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix)
Get namespace index for a given namespace prefix based on current namespace stack in context.
- int [rtXmlNSPush](#) (OSCTXT *pctxt)
Push new namespace prefix mapping level onto stack.
- int [rtXmlNSPop](#) (OSCTXT *pctxt)
Remove top namespace prefix mapping level from stack.
- void [rtXmlNSSetURITable](#) (OSCTXT *pctxt, const OSUTF8CHAR *data[], OSUINT32 nrows)
Set namespace URI table in context.

6.6.1 Detailed Description

XML namespace handling structures and function definitions.

Definition in file [rtXmlNamespace.h](#).

6.6.2 Define Documentation

6.6.2.1 #define RTXMLNSSETQNAME(qname, pNS)

Value:

```
if (0 != pNS) { qname.nsPrefix = pNS->prefix; qname.nsURI = pNS->uri; } \
else { qname.nsPrefix = qname.nsURI = 0; }
```

This macro populates the given QName structure with information from the given namespace structure (namespace URI and prefix).

Parameters:

pqname Pointer to QName structure to be populated. Pointers to items in pNS are assigned directly to fields in pqname. No copies of data are made.

pNS Pointer to namespace structure.

Definition at line 294 of file [rtXmlNamespace.h](#).

6.6.3 Function Documentation

6.6.3.1 OSXMLNamespace* rtXmlNSAddNamespace (OSCTXT * ptxt, OSRTDList * pNSAttrs, const OSUTF8CHAR * prefix, const OSUTF8CHAR * uri)

This function adds a namespace to the context namespace list.

Parameters:

ptxt Pointer to OSCTXT structure

pNSAttrs Namespace attribute list to which namespace info is to be added.

prefix Namespace prefix to be added

uri Namespace URI to be added

Returns:

Pointer to namespace structure or NULL if not added.

6.6.3.2 OSBOOL rtXmlNSEqual (OSXMLNamespace * pNS1, OSXMLNamespace * pNS2)

This function checks if two namespace records are equal.

This does a deep compare in that it will first check if the pointers are equal and then it will check if the contents are equal (same prefix and URI).

Parameters:

pNS1 Pointer to first namespace records to check.

pNS2 Pointer to second record.

Returns:

True if records are equal, false otherwise.

6.6.3.3 void rtXmlNSFreeAttrList (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function frees dynamic memory used to hold namespace attribute values.

Parameters:

pctxt Pointer to OSCTXT structure

pNSAttrs Pointer to namespace attribute list to be freed.

6.6.3.4 const OSUTF8CHAR* rtXmlNSGetAttrQName (OSCTXT * *pctxt*, OSUTF8CHAR * *buf*, size_t *bufsiz*, OSXMLNamespace * *pNS*, const OSUTF8CHAR * *localName*, OSRTDList * *pNSAttrs*)

This function creates a QName for a qualified attribute.

If a prefix is not found for the name, a new namespace entry is created with a generated prefix.

Parameters:

pctxt Pointer to OSCTXT structure

buf Buffer into which qname will be written.

bufsiz Size of the buffer.

pNS Pointer to namespace URI and prefix structure.

localName Local name of the item.

pNSAttrs List of namespace records.

Returns:

Pointer to QName buffer (*buf*).

6.6.3.5 const OSUTF8CHAR* rtXmlNSGetPrefix (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*)

This function gets a namespace prefix assigned to the given URI.

Parameters:

pctxt Pointer to OSCTXT structure

uri Namespace URI to be searched for

Returns:

Pointer to namespace prefix string

6.6.3.6 OSUINT32 rtXmlNSGetPrefixCount (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*)

This function returns the total number of prefixes currently assigned to the given URI.

Parameters:

pctxt Pointer to OSCTXT structure
uri Namespace URI to be searched for

Returns:

Count of prefixes assigned to the URI.

6.6.3.7 int rtXmlNSGetPrefixIndex (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*, const OSUTF8CHAR * *prefix*, OSUINT32 * *pcount*)

This function gets the index of a given prefix in the internal list of prefixes maintained for a given URI in the namespace stack.

It also may return the total number of prefixes currently assigned to the URI.

Parameters:

pctxt Pointer to OSCTXT structure
uri Namespace URI to be searched for
prefix Namespace prefix for which to get index.
pcount Optional pointer to an integer count variable. If provided, the total number of prefixes currently assigned to the URI will be returned.

Returns:

Index to namespace prefix or -1 if the prefix is not assigned to the given URI.

6.6.3.8 const OSUTF8CHAR* rtXmlNSGetPrefixUsingIndex (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*, OSUINT32 *idx*)

This function gets a namespace prefix assigned to the given URI using the given index to select a specific prefix from the URI/prefix map.

Parameters:

pctxt Pointer to OSCTXT structure
uri Namespace URI to be searched for
idx Index to prefix in map. This only has meaning when multiple prefixes have been assigned to the given URI.

Returns:

Pointer to namespace prefix string

6.6.3.9 `const OSUTF8CHAR* rtXmlNSGetQName (OSCTXT * pctxt, OSUTF8CHAR * buf, size_t bufsiz, const OSUTF8CHAR * uri, const OSUTF8CHAR * localName)`

This function creates a QName in the given fixed-size buffer.

If the name will not fit in the buffer, it is truncated.

Parameters:

pctxt Pointer to OSCTXT structure

buf Buffer into which QName will be written.

bufsiz Size of the buffer.

uri Namespace URI.

localName Local name of the item.

Returns:

Pointer to QName buffer (*buf*).

6.6.3.10 `const OSUTF8CHAR* rtXmlNSLookupPrefix (OSCTXT * pctxt, const OSUTF8CHAR * prefix)`

This function looks up a namespace in the context namespace list using the prefix as the key value.

Parameters:

pctxt Pointer to OSCTXT structure

prefix Namespace Prefix to be found.

Returns:

Pointer to namespace URI or NULL if not found.

6.6.3.11 `const OSUTF8CHAR* rtXmlNSLookupPrefixFrag (OSCTXT * pctxt, const OSUTF8CHAR * prefix, size_t prefixLen)`

This function looks up a namespace in the context namespace list using the prefix as the key value.

Parameters:

pctxt Pointer to OSCTXT structure

prefix Namespace Prefix to be found.

prefixLen Namespace Prefix length.

Returns:

Pointer to namespace URI or NULL if not found.

6.6.3.12 OSXMLNamespace* rtXmlNSLookupURI (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*)

This function looks up a namespace in the context namespace stack using URI as the key value.

Parameters:

pctxt Pointer to OSCTXT structure
uri Namespace URI to be found.

Returns:

Pointer to namespace structure or NULL if not found.

6.6.3.13 OSXMLNamespace* rtXmlNSLookupURIInList (OSRTDList * *pNSAttrs*, const OSUTF8CHAR * *uri*)

This function looks up a namespace in the given list using URI as the key value.

Parameters:

pNSAttrs List of namespace records.
uri Namespace URI to be found.

Returns:

Pointer to namespace structure or NULL if not found.

6.6.3.14 const OSUTF8CHAR* rtXmlNSNewPrefix (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*, OSRTDList * *pNSAttrs*)

This function returns the next unused prefix of the form "nsX" where X is a number.

The new namespace declaration is added to the list provided or the context list if a NULL pointer is passed for *pNSAttrs*.

Parameters:

pctxt Pointer to OSCTXT structure
uri Namespace URI
pNSAttrs Pointer to list of namespace attributes.

Returns:

New namespace prefix.

6.6.3.15 void rtXmlNSRemoveAll (OSCTXT * *pctxt*)

This function removes all namespaces from the context namespace list and frees the dynamic memory used to hold the names.

Parameters:

pctxt Pointer to OSCTXT structure

6.6.3.16 OSXMLNamespace* rtXmlNSSetNamespace (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*, const OSUTF8CHAR * *prefix*, const OSUTF8CHAR * *uri*, OSBOOL *override*)

This function sets a namespace in the context namespace list.

If the given namespace URI does not exist in the list, the namespace is added. If the URI is found, the action depends on the value of the override flag. If true, the value of the namespace prefix will be changed to the given prefix. If false, the existing namespace specification is not altered.

Parameters:

pctxt Pointer to OSCTXT structure

pNSAttrs Namespace attribute list to which namespace info is to be added.

prefix Namespace prefix

uri Namespace URI

override Should existing definition be changed?

Returns:

Pointer to namespace structure or NULL if not set.

6.7 rtXmlpCppDecFuncs.h File Reference

XML low-level C++ decode functions.

```
#include "rtxmlsrc/osrtxml.h"
```

```
#include "rtxmlsrc/OSXSDComplexType.h"
```

6.7.1 Detailed Description

XML low-level C++ decode functions.

These are overloaded versions of C XML encode functions for use with C++.

Definition in file [rtXmlpCppDecFuncs.h](#).

Index

- dom
 - [domAddAttribute](#), [95](#)
 - [domAddCdata](#), [96](#)
 - [domAddContent](#), [96](#)
 - [domCreateChild](#), [96](#)
 - [domCreateDocument](#), [97](#)
 - [domFreeDoc](#), [97](#)
 - [domGetAttrData](#), [97](#)
 - [domGetChild](#), [97](#)
 - [domGetDoc](#), [98](#)
 - [domGetElementName](#), [98](#)
 - [domGetNext](#), [98](#)
 - [domGetNextAttr](#), [99](#)
 - [domGetNodeAttributesNum](#), [99](#)
 - [domGetNodeContent](#), [99](#)
 - [domGetNodeFirstAttribute](#), [99](#)
 - [domGetRootElement](#), [100](#)
 - [domParseFile](#), [100](#)
 - [domSaveDoc](#), [100](#)
 - DOM API functions., [94](#)
 - DOM runtime encode/decode functions., [102](#)
 - [domAddAttribute](#)
 - dom, [95](#)
 - [domAddCdata](#)
 - dom, [96](#)
 - [domAddContent](#)
 - dom, [96](#)
 - [domCreateChild](#)
 - dom, [96](#)
 - [domCreateDocument](#)
 - dom, [97](#)
 - [domFreeDoc](#)
 - dom, [97](#)
 - [domGetAttrData](#)
 - dom, [97](#)
 - [domGetChild](#)
 - dom, [97](#)
 - [domGetDoc](#)
 - dom, [98](#)
 - [domGetElementName](#)
 - dom, [98](#)
 - [domGetNext](#)
 - dom, [98](#)
 - [domGetNextAttr](#)
 - dom, [99](#)
 - [domGetNodeAttributesNum](#)
 - dom, [99](#)
 - [domGetNodeContent](#)
 - dom, [99](#)
 - [domGetNodeFirstAttribute](#)
 - dom, [99](#)
 - [domGetRootElement](#)
 - dom, [100](#)
 - [domParseFile](#)
 - dom, [100](#)
 - [domSaveDoc](#)
 - dom, [100](#)
- [osrtdom.h](#), [108](#)
 - [osrxml.h](#), [110](#)
 - [rtSaxGetAttrValue](#), [126](#)
 - [rtSaxGetElemID](#), [126](#)
 - [rtSaxGetElemID8](#), [126](#)
 - [rtSaxHasXMLNSAttrs](#), [127](#)
 - [rtSaxIsEmptyBuffer](#), [127](#)
 - [rtSaxSortAttrs](#), [127](#)
 - [rtSaxStrListMatch](#), [127](#)
 - [rtSaxStrListParse](#), [128](#)
 - [rtXmlCmpBase64Str](#), [128](#)
 - [rtXmlCmpHexStr](#), [128](#)
 - [rtXmlCreateFileInputSource](#), [129](#)
 - [rtXmlInitContext](#), [129](#)
 - [rtXmlInitCtxAppInfo](#), [129](#)
 - [rtXmlMatchBase64Str](#), [129](#)
 - [rtXmlMatchDate](#), [130](#)
 - [rtXmlMatchDateTime](#), [130](#)
 - [rtXmlMatchGDay](#), [130](#)
 - [rtXmlMatchGMonth](#), [130](#)
 - [rtXmlMatchGMonthDay](#), [131](#)
 - [rtXmlMatchGYear](#), [131](#)
 - [rtXmlMatchGYearMonth](#), [131](#)
 - [rtXmlMatchHexStr](#), [131](#)
 - [rtXmlMatchTime](#), [132](#)
 - [rtXmlMemFreeAnyAttrs](#), [132](#)
 - [rtXmlNewQName](#), [132](#)
 - [rtXmlPrepareContext](#), [132](#)
 - [rtXmlSetEncC14N](#), [133](#)
 - [rtXmlSetEncDocHdr](#), [133](#)
 - [rtXmlSetEncodingStr](#), [133](#)
 - [rtXmlSetEncXSINamespace](#), [133](#)

- rtXmlSetFormatting, [134](#)
- rtXmlSetIndent, [134](#)
- rtXmlSetIndentChar, [134](#)
- rtXmlSetNamespacesSet, [135](#)
- rtXmlSetNoNSSchemaLocation, [135](#)
- rtXmlSetNSPrefixLinks, [135](#)
- rtXmlSetSchemaLocation, [135](#)
- rtXmlSetSoapVersion, [136](#)
- rtXmlSetWriteBOM, [136](#)
- rtXmlSetXSISchemaTypeAttr, [136](#)

rtDom

- rtDomAddAttr, [103](#)
- rtDomAddNode, [103](#)
- rtDomAddNSAttrs, [103](#)
- rtDomAddSubTree, [104](#)
- rtDomDecodeDoc, [104](#)
- rtDomEncAny, [105](#)
- rtDomEncAnyAttr, [105](#)
- rtDomEncString, [105](#)
- rtDomEncStringValue, [106](#)
- rtDomEncXSIAttrs, [106](#)
- rtDomSetNode, [106](#)

rtDomAddAttr

- rtDom, [103](#)

rtDomAddNode

- rtDom, [103](#)

rtDomAddNSAttrs

- rtDom, [103](#)

rtDomAddSubTree

- rtDom, [104](#)

rtDomDecodeDoc

- rtDom, [104](#)

rtDomEncAny

- rtDom, [105](#)

rtDomEncAnyAttr

- rtDom, [105](#)

rtDomEncString

- rtDom, [105](#)

rtDomEncStringValue

- rtDom, [106](#)

rtDomEncXSIAttrs

- rtDom, [106](#)

rtDomSetNode

- rtDom, [106](#)

rtSaxGetAttrValue

- osrtxml.h, [126](#)

rtSaxGetElemID

- osrtxml.h, [126](#)

rtSaxGetElemID8

- osrtxml.h, [126](#)

rtSaxHasXMLNSAttrs

- osrtxml.h, [127](#)

rtSaxIsEmptyBuffer

- osrtxml.h, [127](#)

rtSaxSortAttrs

- osrtxml.h, [127](#)

rtSaxStrListMatch

- osrtxml.h, [127](#)

rtSaxStrListParse

- osrtxml.h, [128](#)

rtXmlCmpBase64Str

- osrtxml.h, [128](#)

rtXmlCmpHexStr

- osrtxml.h, [128](#)

rtXmlCreateFileInputSource

- osrtxml.h, [129](#)

rtXmlDec

- rtXmlDecBase64Binary, [8](#)
- rtXmlDecBase64Str, [9](#)
- rtXmlDecBase64StringValue, [9](#)
- rtXmlDecBigInt, [9](#)
- rtXmlDecBool, [10](#)
- rtXmlDecDate, [10](#)
- rtXmlDecDateTime, [10](#)
- rtXmlDecDecimal, [11](#)
- rtXmlDecDouble, [11](#)
- rtXmlDecDynBase64Str, [11](#)
- rtXmlDecDynHexStr, [12](#)
- rtXmlDecDynUTF8Str, [12](#)
- rtXmlDecGDay, [12](#)
- rtXmlDecGMonth, [13](#)
- rtXmlDecGMonthDay, [13](#)
- rtXmlDecGYear, [13](#)
- rtXmlDecGYearMonth, [14](#)
- rtXmlDecHexBinary, [14](#)
- rtXmlDecHexStr, [15](#)
- rtXmlDecInt, [15](#)
- rtXmlDecInt16, [15](#)
- rtXmlDecInt64, [16](#)
- rtXmlDecInt8, [16](#)
- rtXmlDecNSAttr, [16](#)
- rtXmlDecQName, [17](#)
- rtXmlDecTime, [17](#)
- rtXmlDecUInt, [18](#)
- rtXmlDecUInt16, [18](#)
- rtXmlDecUInt64, [18](#)
- rtXmlDecUInt8, [19](#)
- rtXmlDecUTF8Str, [19](#)
- rtXmlDecXmlStr, [19](#)
- rtXmlDecXSIAttr, [20](#)
- rtXmlDecXSIAttrs, [20](#)
- rtXmlParseElementName, [21](#)
- rtXmlParseElemQName, [21](#)

rtXmlDecBase64Binary

- rtXmlDec, [8](#)

rtXmlDecBase64Str

- rtXmlDec, [9](#)

- rtXmlDecBase64StrValue
 - rtXmlDec, [9](#)
- rtXmlDecBigInt
 - rtXmlDec, [9](#)
- rtXmlDecBool
 - rtXmlDec, [10](#)
- rtXmlDecDate
 - rtXmlDec, [10](#)
- rtXmlDecDateTime
 - rtXmlDec, [10](#)
- rtXmlDecDecimal
 - rtXmlDec, [11](#)
- rtXmlDecDouble
 - rtXmlDec, [11](#)
- rtXmlDecDynBase64Str
 - rtXmlDec, [11](#)
- rtXmlDecDynHexStr
 - rtXmlDec, [12](#)
- rtXmlDecDynUTF8Str
 - rtXmlDec, [12](#)
- rtXmlDecGDay
 - rtXmlDec, [12](#)
- rtXmlDecGMonth
 - rtXmlDec, [13](#)
- rtXmlDecGMonthDay
 - rtXmlDec, [13](#)
- rtXmlDecGYear
 - rtXmlDec, [13](#)
- rtXmlDecGYearMonth
 - rtXmlDec, [14](#)
- rtXmlDecHexBinary
 - rtXmlDec, [14](#)
- rtXmlDecHexStr
 - rtXmlDec, [15](#)
- rtXmlDecInt
 - rtXmlDec, [15](#)
- rtXmlDecInt16
 - rtXmlDec, [15](#)
- rtXmlDecInt64
 - rtXmlDec, [16](#)
- rtXmlDecInt8
 - rtXmlDec, [16](#)
- rtXmlDecNSAttr
 - rtXmlDec, [16](#)
- rtXmlDecQName
 - rtXmlDec, [17](#)
- rtXmlDecTime
 - rtXmlDec, [17](#)
- rtXmlDecUInt
 - rtXmlDec, [18](#)
- rtXmlDecUInt16
 - rtXmlDec, [18](#)
- rtXmlDecUInt64
 - rtXmlDec, [18](#)
- rtXmlDecUInt8
 - rtXmlDec, [19](#)
- rtXmlDecUTF8Str
 - rtXmlDec, [19](#)
- rtXmlDecXmlStr
 - rtXmlDec, [19](#)
- rtXmlDecXSIAAttr
 - rtXmlDec, [20](#)
- rtXmlDecXSIAAttrs
 - rtXmlDec, [20](#)
- rtXmlEnc
 - rtXmlEncAny, [28](#)
 - rtXmlEncAnyAttr, [29](#)
 - rtXmlEncAnyTypeValue, [29](#)
 - rtXmlEncBase64Binary, [29](#)
 - rtXmlEncBase64BinaryAttr, [30](#)
 - rtXmlEncBase64StrValue, [30](#)
 - rtXmlEncBigInt, [30](#)
 - rtXmlEncBigIntAttr, [31](#)
 - rtXmlEncBigIntValue, [31](#)
 - rtXmlEncBinStrValue, [32](#)
 - rtXmlEncBitString, [32](#)
 - rtXmlEncBOM, [32](#)
 - rtXmlEncBool, [33](#)
 - rtXmlEncBoolAttr, [33](#)
 - rtXmlEncBoolValue, [33](#)
 - rtXmlEncDate, [34](#)
 - rtXmlEncDateTime, [34](#)
 - rtXmlEncDateTimeValue, [35](#)
 - rtXmlEncDateValue, [35](#)
 - rtXmlEncDecimal, [35](#)
 - rtXmlEncDecimalAttr, [36](#)
 - rtXmlEncDecimalValue, [36](#)
 - rtXmlEncDouble, [36](#)
 - rtXmlEncDoubleAttr, [37](#)
 - rtXmlEncDoubleValue, [37](#)
 - rtXmlEncEmptyElement, [38](#)
 - rtXmlEncEndDocument, [38](#)
 - rtXmlEncEndElement, [38](#)
 - rtXmlEncEndSoapElems, [39](#)
 - rtXmlEncEndSoapEnv, [39](#)
 - rtXmlEncFloat, [39](#)
 - rtXmlEncFloatAttr, [40](#)
 - rtXmlEncGDay, [40](#)
 - rtXmlEncGDayValue, [41](#)
 - rtXmlEncGMonth, [41](#)
 - rtXmlEncGMonthDay, [41](#)
 - rtXmlEncGMonthDayValue, [42](#)
 - rtXmlEncGMonthValue, [42](#)
 - rtXmlEncGYear, [42](#)
 - rtXmlEncGYearMonth, [43](#)
 - rtXmlEncGYearMonthValue, [43](#)
 - rtXmlEncGYearValue, [43](#)
 - rtXmlEncHexBinary, [44](#)

- rtXmlEncHexBinaryAttr, [44](#)
- rtXmlEncHexStrValue, [45](#)
- rtXmlEncIndent, [45](#)
- rtXmlEncInt, [45](#)
- rtXmlEncInt64, [46](#)
- rtXmlEncInt64Attr, [46](#)
- rtXmlEncInt64Value, [46](#)
- rtXmlEncIntAttr, [47](#)
- rtXmlEncIntPattern, [47](#)
- rtXmlEncIntValue, [48](#)
- rtXmlEncNamedBits, [48](#)
- rtXmlEncNSAttrs, [48](#)
- rtXmlEncReal10, [49](#)
- rtXmlEncSoapArrayTypeAttr, [49](#)
- rtXmlEncStartDocument, [50](#)
- rtXmlEncStartElement, [50](#)
- rtXmlEncStartSoapElems, [50](#)
- rtXmlEncStartSoapEnv, [51](#)
- rtXmlEncString, [51](#)
- rtXmlEncStringValue, [51](#)
- rtXmlEncStringValue2, [52](#)
- rtXmlEncTermStartElement, [52](#)
- rtXmlEncTime, [52](#)
- rtXmlEncTimeValue, [53](#)
- rtXmlEncUInt, [53](#)
- rtXmlEncUInt64, [54](#)
- rtXmlEncUInt64Attr, [54](#)
- rtXmlEncUInt64Value, [54](#)
- rtXmlEncUIntAttr, [55](#)
- rtXmlEncUIntValue, [55](#)
- rtXmlEncUnicodeStr, [55](#)
- rtXmlEncUTF8Attr, [56](#)
- rtXmlEncUTF8Attr2, [56](#)
- rtXmlEncUTF8Str, [57](#)
- rtXmlEncXSIAattrs, [57](#)
- rtXmlEncXSITypeAttr, [57](#)
- rtXmlFreeInputSource, [58](#)
- rtXmlGetEncBufLen, [28](#)
- rtXmlGetEncBufPtr, [28](#)
- rtXmlGetIndent, [58](#)
- rtXmlGetIndentChar, [58](#)
- rtXmlGetWriteBOM, [58](#)
- rtXmlPrintNSAttrs, [59](#)
- rtXmlSetEncBufPtr, [59](#)
- rtXmlEncAny
 - rtXmlEnc, [28](#)
- rtXmlEncAnyAttr
 - rtXmlEnc, [29](#)
- rtXmlEncAnyTypeValue
 - rtXmlEnc, [29](#)
- rtXmlEncAttrC14N
 - rtXmlpDec, [65](#)
- rtXmlEncBase64Binary
 - rtXmlEnc, [29](#)
- rtXmlEncBase64BinaryAttr
 - rtXmlEnc, [30](#)
- rtXmlEncBase64StrValue
 - rtXmlEnc, [30](#)
- rtXmlEncBigInt
 - rtXmlEnc, [30](#)
- rtXmlEncBigIntAttr
 - rtXmlEnc, [31](#)
- rtXmlEncBigIntValue
 - rtXmlEnc, [31](#)
- rtXmlEncBinStrValue
 - rtXmlEnc, [32](#)
- rtXmlEncBitString
 - rtXmlEnc, [32](#)
- rtXmlEncBOM
 - rtXmlEnc, [32](#)
- rtXmlEncBool
 - rtXmlEnc, [33](#)
- rtXmlEncBoolAttr
 - rtXmlEnc, [33](#)
- rtXmlEncBoolValue
 - rtXmlEnc, [33](#)
- rtXmlEncDate
 - rtXmlEnc, [34](#)
- rtXmlEncDateTime
 - rtXmlEnc, [34](#)
- rtXmlEncDateTimeValue
 - rtXmlEnc, [35](#)
- rtXmlEncDateValue
 - rtXmlEnc, [35](#)
- rtXmlEncDecimal
 - rtXmlEnc, [35](#)
- rtXmlEncDecimalAttr
 - rtXmlEnc, [36](#)
- rtXmlEncDecimalValue
 - rtXmlEnc, [36](#)
- rtXmlEncDouble
 - rtXmlEnc, [36](#)
- rtXmlEncDoubleAttr
 - rtXmlEnc, [37](#)
- rtXmlEncDoubleValue
 - rtXmlEnc, [37](#)
- rtXmlEncEmptyElement
 - rtXmlEnc, [38](#)
- rtXmlEncEndDocument
 - rtXmlEnc, [38](#)
- rtXmlEncEndElement
 - rtXmlEnc, [38](#)
- rtXmlEncEndSoapElems
 - rtXmlEnc, [39](#)
- rtXmlEncEndSoapEnv
 - rtXmlEnc, [39](#)
- rtXmlEncFloat
 - rtXmlEnc, [39](#)

rtXmlEncFloatAttr	rtXmlEnc, 40	rtXmlEncStartElement	rtXmlEnc, 50
rtXmlEncGDay	rtXmlEnc, 40	rtXmlEncStartSoapElems	rtXmlEnc, 50
rtXmlEncGDayValue	rtXmlEnc, 41	rtXmlEncStartSoapEnv	rtXmlEnc, 51
rtXmlEncGMonth	rtXmlEnc, 41	rtXmlEncString	rtXmlEnc, 51
rtXmlEncGMonthDay	rtXmlEnc, 41	rtXmlEncStringValue	rtXmlEnc, 51
rtXmlEncGMonthDayValue	rtXmlEnc, 42	rtXmlEncStringValue2	rtXmlEnc, 52
rtXmlEncGMonthValue	rtXmlEnc, 42	rtXmlEncTermStartElement	rtXmlEnc, 52
rtXmlEncGYear	rtXmlEnc, 42	rtXmlEncTime	rtXmlEnc, 52
rtXmlEncGYearMonth	rtXmlEnc, 43	rtXmlEncTimeValue	rtXmlEnc, 53
rtXmlEncGYearMonthValue	rtXmlEnc, 43	rtXmlEncUInt	rtXmlEnc, 53
rtXmlEncGYearValue	rtXmlEnc, 43	rtXmlEncUInt64	rtXmlEnc, 54
rtXmlEncHexBinary	rtXmlEnc, 44	rtXmlEncUInt64Attr	rtXmlEnc, 54
rtXmlEncHexBinaryAttr	rtXmlEnc, 44	rtXmlEncUInt64Value	rtXmlEnc, 54
rtXmlEncHexStringValue	rtXmlEnc, 45	rtXmlEncUIntAttr	rtXmlEnc, 55
rtXmlEncIndent	rtXmlEnc, 45	rtXmlEncUIntValue	rtXmlEnc, 55
rtXmlEncInt	rtXmlEnc, 45	rtXmlEncUnicodeStr	rtXmlEnc, 55
rtXmlEncInt64	rtXmlEnc, 46	rtXmlEncUTF8Attr	rtXmlEnc, 56
rtXmlEncInt64Attr	rtXmlEnc, 46	rtXmlEncUTF8Attr2	rtXmlEnc, 56
rtXmlEncInt64Value	rtXmlEnc, 46	rtXmlEncUTF8Str	rtXmlEnc, 57
rtXmlEncIntAttr	rtXmlEnc, 47	rtXmlEncXSIAttrs	rtXmlEnc, 57
rtXmlEncIntPattern	rtXmlEnc, 47	rtXmlEncXSITypeAttr	rtXmlEnc, 57
rtXmlEncIntValue	rtXmlEnc, 48	rtXmlErrCodes.h, 137	
rtXmlEncNamedBits	rtXmlEnc, 48	rtXmlExternDefs.h, 139	
rtXmlEncNSAttrs	rtXmlEnc, 48	rtXmlFreeInputSource	rtXmlEnc, 58
rtXmlEncReal10	rtXmlEnc, 49	rtXmlGetEncBufLen	rtXmlEnc, 28
rtXmlEncSoapArrayTypeAttr	rtXmlEnc, 49	rtXmlGetEncBufPtr	rtXmlEnc, 28
rtXmlEncStartDocument	rtXmlEnc, 50	rtXmlGetIndent	rtXmlEnc, 58
		rtXmlGetIndentChar	rtXmlEnc, 58

- rtXmlGetWriteBOM
 - rtXmlEnc, 58
- rtXmlInitContext
 - osrtxml.h, 129
- rtXmlInitCtxtAppInfo
 - osrtxml.h, 129
- rtXmlKeyArray.h, 140
- rtXmlMatchBase64Str
 - osrtxml.h, 129
- rtXmlMatchDate
 - osrtxml.h, 130
- rtXmlMatchDateTime
 - osrtxml.h, 130
- rtXmlMatchGDay
 - osrtxml.h, 130
- rtXmlMatchGMonth
 - osrtxml.h, 130
- rtXmlMatchGMonthDay
 - osrtxml.h, 131
- rtXmlMatchGYear
 - osrtxml.h, 131
- rtXmlMatchGYearMonth
 - osrtxml.h, 131
- rtXmlMatchHexStr
 - osrtxml.h, 131
- rtXmlMatchTime
 - osrtxml.h, 132
- rtXmlMemFreeAnyAttrs
 - osrtxml.h, 132
- rtXmlNamespace.h, 141
 - rtXmlNSAddNamespace, 143
 - rtXmlNSEqual, 143
 - rtXmlNSFreeAttrList, 144
 - rtXmlNSGetAttrQName, 144
 - rtXmlNSGetPrefix, 144
 - rtXmlNSGetPrefixCount, 144
 - rtXmlNSGetPrefixIndex, 145
 - rtXmlNSGetPrefixUsingIndex, 145
 - rtXmlNSGetQName, 145
 - rtXmlNSLookupPrefix, 146
 - rtXmlNSLookupPrefixFrag, 146
 - rtXmlNSLookupURI, 146
 - rtXmlNSLookupURIInList, 147
 - rtXmlNSNewPrefix, 147
 - rtXmlNSRemoveAll, 147
 - rtXmlNSSetNamespace, 147
 - RTXMLNSSETQNAME, 143
- rtXmlNewQName
 - osrtxml.h, 132
- rtXmlNSAddNamespace
 - rtXmlNamespace.h, 143
- rtXmlNSEqual
 - rtXmlNamespace.h, 143
- rtXmlNSFreeAttrList
 - rtXmlNamespace.h, 144
- rtXmlNSGetAttrQName
 - rtXmlNamespace.h, 144
- rtXmlNSGetPrefix
 - rtXmlNamespace.h, 144
- rtXmlNSGetPrefixCount
 - rtXmlNamespace.h, 144
- rtXmlNSGetPrefixIndex
 - rtXmlNamespace.h, 145
- rtXmlNSGetPrefixUsingIndex
 - rtXmlNamespace.h, 145
- rtXmlNSGetQName
 - rtXmlNamespace.h, 145
- rtXmlNSLookupPrefix
 - rtXmlNamespace.h, 146
- rtXmlNSLookupPrefixFrag
 - rtXmlNamespace.h, 146
- rtXmlNSLookupURI
 - rtXmlNamespace.h, 146
- rtXmlNSLookupURIInList
 - rtXmlNamespace.h, 147
- rtXmlNSNewPrefix
 - rtXmlNamespace.h, 147
- rtXmlNSRemoveAll
 - rtXmlNamespace.h, 147
- rtXmlNSSetNamespace
 - rtXmlNamespace.h, 147
- RTXMLNSSETQNAME
 - rtXmlNamespace.h, 143
- rtXmlParseElementName
 - rtXmlDec, 21
- rtXmlParseElemQName
 - rtXmlDec, 21
- rtXmlpCountListItems
 - rtXmlpDec, 66
- rtXmlpCppDecFuncs.h, 149
- rtXmlpCreateReader
 - rtXmlpDec, 66
- rtXmlpDec
 - rtXmlEncAttrC14N, 65
 - rtXmlpCountListItems, 66
 - rtXmlpCreateReader, 66
 - rtXmlpDecAny, 66
 - rtXmlpDecAnyAttrStr, 66
 - rtXmlpDecAnyElem, 67
 - rtXmlpDecBase64Str, 67
 - rtXmlpDecBigInt, 68
 - rtXmlpDecBitString, 68
 - rtXmlpDecBool, 69
 - rtXmlpDecDate, 69
 - rtXmlpDecDateTime, 69
 - rtXmlpDecDecimal, 70
 - rtXmlpDecDouble, 70
 - rtXmlpDecDynBase64Str, 70

rtXmlpDecDynBitString, 71
 rtXmlpDecDynHexStr, 71
 rtXmlpDecDynUnicodeStr, 71
 rtXmlpDecDynUTF8Str, 72
 rtXmlpDecGDay, 72
 rtXmlpDecGMonth, 73
 rtXmlpDecGMonthDay, 73
 rtXmlpDecGYear, 73
 rtXmlpDecGYearMonth, 74
 rtXmlpDecHexStr, 74
 rtXmlpDecInt, 74
 rtXmlpDecInt16, 75
 rtXmlpDecInt64, 75
 rtXmlpDecInt8, 75
 rtXmlpDecNamedBits, 76
 rtXmlpDecStrList, 76
 rtXmlpDecTime, 77
 rtXmlpDecUInt, 77
 rtXmlpDecUInt16, 77
 rtXmlpDecUInt64, 78
 rtXmlpDecUInt8, 78
 rtXmlpDecUTF8Str, 78
 rtXmlpDecXmlStr, 79
 rtXmlpDecXmlStrList, 79
 rtXmlpDecXSIAAttr, 79
 rtXmlpDecXSIAAttrs, 80
 rtXmlpDecXSISchemaAttr, 80
 rtXmlpForceDecodeAsGroup, 80
 rtXmlpGetAttributeCount, 81
 rtXmlpGetAttributeID, 81
 rtXmlpGetCurrentLevel, 81
 rtXmlpGetNextAllElemID, 82
 rtXmlpGetNextAllElemID16, 82
 rtXmlpGetNextElem, 83
 rtXmlpGetNextElemID, 83
 rtXmlpGetNextSeqElemID, 83
 rtXmlpGetXmInAttrs, 84
 rtXmlpGetXSISchemaAttr, 84
 rtXmlpGetXSISchemaIndex, 85
 rtXmlpHasAttributes, 85
 rtXmlpHideAttributes, 85
 rtXmlpIsDecodeAsGroup, 85
 rtXmlpIsEmptyElement, 86
 rtXmlpIsLastEventDone, 86
 rtXmlpIsUTF8Encoding, 86
 rtXmlpListHasItem, 87
 rtXmlpLookupXSISchemaIndex, 87
 rtXmlpMarkLastEventActive, 87
 rtXmlpMarkPos, 87
 rtXmlpMatchEndTag, 88
 rtXmlpMatchStartTag, 88
 rtXmlpNeedDecodeAttributes, 88
 rtXmlpResetMarkedPos, 89
 rtXmlpRewindToMarkedPos, 89
 rtXmlpSelectAttribute, 89
 rtXmlpSetListMode, 89
 rtXmlpSetMixedContentMode, 89
 rtXmlpSetNamespaceTable, 90
 rtXmlpSetWhiteSpaceMode, 90
 rtXmlpDecAny
 rtXmlpDec, 66
 rtXmlpDecAnyAttrStr
 rtXmlpDec, 66
 rtXmlpDecAnyElem
 rtXmlpDec, 67
 rtXmlpDecBase64Str
 rtXmlpDec, 67
 rtXmlpDecBigInt
 rtXmlpDec, 68
 rtXmlpDecBitString
 rtXmlpDec, 68
 rtXmlpDecBool
 rtXmlpDec, 69
 rtXmlpDecDate
 rtXmlpDec, 69
 rtXmlpDecDateTime
 rtXmlpDec, 69
 rtXmlpDecDecimal
 rtXmlpDec, 70
 rtXmlpDecDouble
 rtXmlpDec, 70
 rtXmlpDecDynBase64Str
 rtXmlpDec, 70
 rtXmlpDecDynBitString
 rtXmlpDec, 71
 rtXmlpDecDynHexStr
 rtXmlpDec, 71
 rtXmlpDecDynUnicodeStr
 rtXmlpDec, 71
 rtXmlpDecDynUTF8Str
 rtXmlpDec, 72
 rtXmlpDecGDay
 rtXmlpDec, 72
 rtXmlpDecGMonth
 rtXmlpDec, 73
 rtXmlpDecGMonthDay
 rtXmlpDec, 73
 rtXmlpDecGYear
 rtXmlpDec, 73
 rtXmlpDecGYearMonth
 rtXmlpDec, 74
 rtXmlpDecHexStr
 rtXmlpDec, 74
 rtXmlpDecInt
 rtXmlpDec, 74
 rtXmlpDecInt16
 rtXmlpDec, 75
 rtXmlpDecInt64

rtXmlpDec, 75	rtXmlpDec, 85
rtXmlpDecInt8	rtXmlpHideAttributes
rtXmlpDec, 75	rtXmlpDec, 85
rtXmlpDecNamedBits	rtXmlpIsDecodeAsGroup
rtXmlpDec, 76	rtXmlpDec, 85
rtXmlpDecStrList	rtXmlpIsEmptyElement
rtXmlpDec, 76	rtXmlpDec, 86
rtXmlpDecTime	rtXmlpIsLastEventDone
rtXmlpDec, 77	rtXmlpDec, 86
rtXmlpDecUInt	rtXmlpIsUTF8Encoding
rtXmlpDec, 77	rtXmlpDec, 86
rtXmlpDecUInt16	rtXmlpListHasItem
rtXmlpDec, 77	rtXmlpDec, 87
rtXmlpDecUInt64	rtXmlpLookupXSITypeIndex
rtXmlpDec, 78	rtXmlpDec, 87
rtXmlpDecUInt8	rtXmlpMarkLastEventActive
rtXmlpDec, 78	rtXmlpDec, 87
rtXmlpDecUTF8Str	rtXmlpMarkPos
rtXmlpDec, 78	rtXmlpDec, 87
rtXmlpDecXmlStr	rtXmlpMatchEndTag
rtXmlpDec, 79	rtXmlpDec, 88
rtXmlpDecXmlStrList	rtXmlpMatchStartTag
rtXmlpDec, 79	rtXmlpDec, 88
rtXmlpDecXSIAAttr	rtXmlpNeedDecodeAttributes
rtXmlpDec, 79	rtXmlpDec, 88
rtXmlpDecXSIAAttrs	rtXmlPrepareContext
rtXmlpDec, 80	osrtxml.h, 132
rtXmlpDecXSITypeAttr	rtXmlpResetMarkedPos
rtXmlpDec, 80	rtXmlpDec, 89
rtXmlpForceDecodeAsGroup	rtXmlpRewindToMarkedPos
rtXmlpDec, 80	rtXmlpDec, 89
rtXmlpGetAttributeCount	rtXmlPrintNSAttrs
rtXmlpDec, 81	rtXmlEnc, 59
rtXmlpGetAttributeID	rtXmlpSelectAttribute
rtXmlpDec, 81	rtXmlpDec, 89
rtXmlpGetCurrentLevel	rtXmlpSetListMode
rtXmlpDec, 81	rtXmlpDec, 89
rtXmlpGetNextAllElemID	rtXmlpSetMixedContentMode
rtXmlpDec, 82	rtXmlpDec, 89
rtXmlpGetNextAllElemID16	rtXmlpSetNamespaceTable
rtXmlpDec, 82	rtXmlpDec, 90
rtXmlpGetNextElem	rtXmlpSetWhiteSpaceMode
rtXmlpDec, 83	rtXmlpDec, 90
rtXmlpGetNextElemID	rtXmlSetEncBufPtr
rtXmlpDec, 83	rtXmlEnc, 59
rtXmlpGetNextSeqElemID	rtXmlSetEncC14N
rtXmlpDec, 83	osrtxml.h, 133
rtXmlpGetXmlnsAttrs	rtXmlSetEncDocHdr
rtXmlpDec, 84	osrtxml.h, 133
rtXmlpGetXSITypeAttr	rtXmlSetEncodingStr
rtXmlpDec, 84	osrtxml.h, 133
rtXmlpGetXSITypeIndex	rtXmlSetEncXSINamespace
rtXmlpDec, 85	osrtxml.h, 133
rtXmlpHasAttributes	rtXmlSetFormatting

- osrtxml.h, [134](#)
- rtXmlSetIndent
 - osrtxml.h, [134](#)
- rtXmlSetIndentChar
 - osrtxml.h, [134](#)
- rtXmlSetNamespacesSet
 - osrtxml.h, [135](#)
- rtXmlSetNoNSSchemaLocation
 - osrtxml.h, [135](#)
- rtXmlSetNSPrefixLinks
 - osrtxml.h, [135](#)
- rtXmlSetSchemaLocation
 - osrtxml.h, [135](#)
- rtXmlSetSoapVersion
 - osrtxml.h, [136](#)
- rtXmlSetWriteBOM
 - osrtxml.h, [136](#)
- rtXmlSetXSITypeAttr
 - osrtxml.h, [136](#)
- rtXmlUtil
 - rtXmlWriteToFile, [60](#)
- rtXmlWriteToFile
 - rtXmlUtil, [60](#)

- XML_E_TAGMISMATCH, [93](#)
- XML_OK_EOB, [93](#)
- XML_OK_FRAG, [93](#)

- XML decode functions., [6](#)
- XML encode functions., [22](#)
- XML pull-parser decode functions., [61](#)
- XML run-time error status codes., [91](#)
- XML utility functions., [60](#)
- XML_E_BASE
 - xmlErrCodes, [92](#)
- XML_E_ELEMMISRQ
 - xmlErrCodes, [92](#)
- XML_E_ELEMSMISRQ
 - xmlErrCodes, [92](#)
- XML_E_FLDABSENT
 - xmlErrCodes, [93](#)
- XML_E_NOMATCH
 - xmlErrCodes, [93](#)
- XML_E_NSURINOTFOU
 - xmlErrCodes, [93](#)
- XML_E_TAGMISMATCH
 - xmlErrCodes, [93](#)
- XML_OK_EOB
 - xmlErrCodes, [93](#)
- XML_OK_FRAG
 - xmlErrCodes, [93](#)
- xmlErrCodes
 - XML_E_BASE, [92](#)
 - XML_E_ELEMMISRQ, [92](#)
 - XML_E_ELEMSMISRQ, [92](#)
 - XML_E_FLDABSENT, [93](#)
 - XML_E_NOMATCH, [93](#)
 - XML_E_NSURINOTFOU, [93](#)